

7.Understanding Working of NFS

NFS is a protocol for remote access to a file system developed by Sun

- It does not implement a file system per se
- Remote access is transparent to applications
- File system and OS independent
- Client/server architecture
- Client file system requests are forwarded to a remote server; NFS follows the remote access model – Requests are implemented as remote procedure calls (RPCs)

Servers:

File sharing Server's:


- 1. NFS: Network File System:** These servers are used in LAN
- 2. FTP: File Transfer Protocol:** These servers are used in WAN & LAN
- 3. Samba Server:** These servers are used in Linux & Window heterogeneous networks.

Note: 1. NFS is used in LAN because bandwidth for NFS is more than compared with FTP and Samba.
2. STP is used in WAN because FTP requires very less bandwidth when compared to NFS.

NFS (Network File

System):-**Configuration Steps:**

- 1) Copy all the shared files to a single location
 - /nfsshare aa bb cc
- 2) Create new file inside the share directory
 - aa bb cc
- 3) Packages:
 - i) nfs-utils: to un-install the nfs-utils 60
 - ii) portmap (please do not uninstall portmap)
- 4)services
 - nfsportmap
- 5) Daemons:
 - nfs d quota d mount d
- 6) Main Configuration File: /etc/exports



Experiment:

Make a directory named nfsshare with files aa bb cc:

```
#mkdir /nfsshare
```

```
#cd /nfsshare
```

```
#touch aa bb cc
```

```
#ls
```

```
aa
```

```
bb
```

```
cc
```

Check if the nfs-utils package is installed or not:

```
#rpm -q nfs-utils (Prints a message whether package is installed or not)
```

```
#rpm -q portmap
```

To reinstall the package first remove it with the following commands:

```
#servicesnfs stop
```

```
#rpm -e nfs-utils
```

```
#rm -rf /var/lib/nfs/xtab----- remove
```

If package is not installed then there are two ways to install:

```
61
```

1. Download from FTP and install

```
#ping the server
```

```
#rpm -ivhftp://192.168.0.250:/pub.RedHat/RPMS/nfs* --force -aid
```

2. Install from CD

```
#mount /dev/cdrom/mnt
```

```
#cd /mnt
```

```
#ls
```

```
#cd Fedora
```

#cd RPMS

#rpm -ivhnfs-utils* --force -aid

#rpm -ivhportmap* --force -aid

After installing the nfs-utils package create file as below:

#vi /etc/exports

/var/ftp/pub 192.168.0.0/24(ro,sync)

/nfsshare 192.168.0.0.24(rw,sync)

Note:in vi-editor write this content (/nfsshare server ipaddress and no. of systems that are connected in network)

After installing services enter the command to restart

#servicesnfs restart

Note: execute this command twice because first it will show failed second time it will show ok.

Access to NFS share from client:

#mount -t nfs 10.10.12.114:/nfsshare/mnt

Note: In client machine enter Server Ipaddress

Note:

1) #ping 192.168.0.3 -b

Broadcasts the address in the network only.

2) #ssh 192.168.0.8

Connects the PC to another PC just like Terminal connection in Windows.

3) In NFS all files & Directory are by default in read only mode.

Common KVM Switch: Using a KVM switch a monitor, keyboard, and a mouse can be connected to two computers.