

Welcome to Ubuntu 14.04.5 LTS (GNU/Linux 4.4.0-71-generic x86\_64)

\* Documentation: <https://help.ubuntu.com/>

565 packages can be updated.  
211 updates are security updates.

New release '16.04.4 LTS' available.  
Run 'do-release-upgrade' to upgrade to it.

Your Hardware Enablement Stack (HWE) is supported until April 2019.

Last login: Tue Apr 24 19:15:48 2018 from 10.18.131.204

cloe@spike:~\$ cd src/

cloe@spike:~/src\$ ls

d2xxDriverInVocore hello release test vocoreUART\_read vocoreUSBdriver

cloe@spike:~/src\$ cd d2xxDriverInVocore/

cloe@spike:~/src/d2xxDriverInVocore\$ ls

build ftd2xx.h Makefile.make ReadMe.txt WinTypes.h

examples libusb README.md release-notes.txt

cloe@spike:~/src/d2xxDriverInVocore\$ cd examples/

cloe@spike:~/src/d2xxDriverInVocore/examples\$ ls

BitMode ftd2xx.h Makefile SetVIDPID Timeouts write

EEPROM LargeRead MultiThread Simple W32

Events loopback Rules.make static WinTypes.h

cloe@spike:~/src/d2xxDriverInVocore/examples\$ cd Simple/

cloe@spike:~/src/d2xxDriverInVocore/examples/Simple\$ ls

main.c Makefile

cloe@spike:~/src/d2xxDriverInVocore/examples/Simple\$ make

/home/cloe/openwrt/staging\_dir/toolchain-mipsel\_24kec+dsp\_gcc-4.8-linaro\_uClibc-0.9.33.2/bin/mipsel-

openwrt-linux-gcc -g main.c -o d2xxUSBdriver -L/home/cloe/openwrt/staging\_dir/target-

mipsel\_24kec+dsp\_uClibc-0.9.33.2/usr/lib -lftd2xx -Wall -Wextra -lrt

mipsel-openwrt-linux-gcc: warning: environment variable 'STAGING\_DIR' not defined

mipsel-openwrt-linux-gcc: warning: environment variable 'STAGING\_DIR' not defined

mipsel-openwrt-linux-gcc: warning: environment variable 'STAGING\_DIR' not defined

/home/cloe/openwrt/staging\_dir/target-mipsel\_24kec+dsp\_uClibc-0.9.33.2/usr/lib/libftd2xx.so: error adding

symbols: File in wrong format

collect2: error: ld returned 1 exit status

make: \*\*\* [main] Error 1

cloe@spike:~/src/d2xxDriverInVocore/examples/Simple\$ vi Makefile

cloe@spike:~/src/d2xxDriverInVocore/examples/Simple\$