

library is designed to provide a simple interface for input–output for beginners. As you continue through the chapters in this book, you will acquire the knowledge and skills to create your own library. You are free to modify and reuse the library, as long as you give credit to its original author. Another alternative, which we will discuss in Chapter 13, is to call Standard C library functions from your assembly language programs. Again, that requires some additional background.

Table 5-1 contains a complete list of procedures in the Irvine32 library.

TABLE 5-1 Procedures in the Irvine32 Library.

Procedure	Description
CloseFile	Closes a disk file that was previously opened.
Clsrscr	Clears the console window and locates the cursor at the upper left corner.
CreateOutputFile	Creates a new disk file for writing in output mode.
Crlf	Writes an end-of-line sequence to the console window.
Delay	Pauses the program execution for a specified <i>n</i> -millisecond interval.
DumpMem	Writes a block of memory to the console window in hexadecimal.
DumpRegs	Displays the EAX, EBX, ECX, EDX, ESI, EDI, EBP, ESP, EFLAGS, and EIP registers in hexadecimal. Also displays the most common CPU status flags.
GetCommandTail	Copies the program's command-line arguments (called the <i>command tail</i>) into an array of bytes.
GetDateTime	Gets the current date and time from the system.
GetMaxXY	Gets the number of columns and rows in the console window's buffer.
GetMseconds	Returns the number of milliseconds elapsed since midnight.
GetTextColor	Returns the active foreground and background text colors in the console window.
Gotoxy	Locates the cursor at a specific row and column in the console window.
IsDigit	Sets the Zero flag if the AL register contains the ASCII code for a decimal digit (0–9).
MsgBox	Displays a popup message box.
MsgBoxAsk	Display a yes/no question in a popup message box.
OpenInputFile	Opens an existing disk file for input.
ParseDecimal32	Converts an unsigned decimal integer string to 32-bit binary.
ParseInteger32	Converts a signed decimal integer string to 32-bit binary.
Random32	Generates a 32-bit pseudorandom integer in the range 0 to FFFFFFFFh.
Randomize	Seeds the random number generator with a unique value.
RandomRange	Generates a pseudorandom integer within a specified range.
ReadChar	Waits for a single character to be typed at the keyboard and returns the character.
ReadDec	Reads an unsigned 32-bit decimal integer from the keyboard, terminated by the Enter key.
ReadFromFile	Reads an input disk file into a buffer.
ReadHex	Reads a 32-bit hexadecimal integer from the keyboard, terminated by the Enter key.

Table 5-1 (Continued)

Procedure	Description
ReadInt	Reads a 32-bit signed decimal integer from the keyboard, terminated by the Enter key.
ReadKey	Reads a character from the keyboard's input buffer without waiting for input.
ReadString	Reads a string from the keyboard, terminated by the Enter key.
SetTextColor	Sets the foreground and background colors of all subsequent text output to the console.
Str_compare	Compares two strings.
Str_copy	Copies a source string to a destination string.
Str_length	Returns the length of a string in EAX.
Str_trim	Removes unwanted characters from a string.
Str_ucase	Converts a string to uppercase letters.
WaitMsg	Displays a message and waits for a key to be pressed.
WriteBin	Writes an unsigned 32-bit integer to the console window in ASCII binary format.
WriteBinB	Writes a binary integer to the console window in byte, word, or doubleword format.
WriteChar	Writes a single character to the console window.
WriteDec	Writes an unsigned 32-bit integer to the console window in decimal format.
WriteHex	Writes a 32-bit integer to the console window in hexadecimal format.
WriteHexB	Writes a byte, word, or doubleword integer to the console window in hexadecimal format.
WriteInt	Writes a signed 32-bit integer to the console window in decimal format.
WriteStackFrame	Writes the current procedure's stack frame to the console.
WriteStackFrameName	Writes the current procedure's name and stack frame to the console.
WriteString	Writes a null-terminated string to the console window.
WriteToFile	Writes a buffer to an output file.
WriteWindowsMsg	Displays a string containing the most recent error generated by MS-Windows.

5.4.2 Overview

Console Window The *console window* (or *command window*) is a text-only window created by MS-Windows when a command prompt is displayed.

To display a console window in Microsoft Windows, click the Start button on the desktop, type *cmd* into the *Start Search* field, and press Enter. Once a console window is open, you can resize the console window buffer by right-clicking on the system menu in the window's upper-left corner, selecting *Properties* from the popup menu, and then modifying the values, as shown in Fig. 5-10.

You can also select various font sizes and colors. The console window defaults to 25 rows by 80 columns. You can use the *mode* command to change the number of columns and lines. The following, typed at the command prompt, sets the console window to 40 columns by 30 lines:

```
mode con cols=40 lines=30
```