

Configure Tenant System Settings Profiles




For supported software information, click [here](#).


System settings profiles allow you configure tenant-level system settings profiles and use them in a basic master profile or a system subprofile.

To configure a tenant system settings profile:

1. Go to Configure > SD-WAN > Profile Elements > Policies > System > System Settings.



The following screen displays.



2. Click + Settings to add a settings profile. The Create Settings page displays. In the General tab, enter information for the following fields.

The screenshot shows the 'Create Settings' page. The header includes the title 'Create Settings' and the breadcrumb trail 'Configure > Profile Elements > Policies > System > Settings'. Below the header, there are three tabs: 'General' (highlighted with a red box), 'Settings', and 'Permissions'. The 'General' tab contains the following fields:

- Name:** A text input field with a 'Version 1' label to its right.
- Description:** A text input field.
- Type:** A dropdown menu with 'Settings' selected.
- Tags:** A text input field with the prompt 'Press Enter to add'.

At the bottom of the page, there are two buttons: 'Close' and 'Next'.

Field	Description
Name (Required)	Enter a name for the settings profile.
Description	Enter a text description for the settings profile.
Tags	Enter one or more tags. A tag is an alphanumeric text descriptor with no spaces or special characters. You can specify multiple tags for the same profile. The tags are used for searching objects.

- Click Next or select the Settings tab, and then select the time zone for the tenant settings profile.

Create Settings

Configure > Profile Elements > Policies > System > Settings

General **Settings** Permissions

Time Zone

Select Time Zone

- Australia/Broken_Hill
- Australia/Currie
- Australia/Darwin
- Australia/Eucla
- Australia/Hobart
- Australia/Lindeman
- Australia/Lord_Howe
- Australia/Melbourne
- Australia/Perth

Cancel Next

- Click Next or select the Permissions tab to set or update the permission for each role. The default permission for each role is preselected and you can update it. The roles are Enterprise Administrator, Enterprise Operator, Service Provider Administrator, and Service Provider Operator. The role permissions are Edit, Hide, and Read.

Create Settings

Configure > Profile Elements > Policies > System > Settings

General

Settings

Permissions

Enterprise Administrator	(Reset)	Read	▼
Service Provider Administrator (Inherited)		Edit	▼
Service Provider Operator (Inherited)		Read	▼
Enterprise Operator (Inherited)		Read	▼

Cancel

Save

5. Click Save.

You can associate a system settings profile with a basic master profile or a system subprofile. For more information, see [Configure Profiles](#).

Supported Software Information

Releases 12.1.1 and later support all content described in this article.

Additional Information

[Configure Profiles](#)