


Enable SMS Text Messaging

 For supported software information, click [here](#).

To configure Versa Director to send SMS text messages to a mobile phone to communicate network events:

1. Create an SMS services account with Plivo. Plivo is the only SMS services provider currently supported by Versa Director. For information about creating a Plivo account, see <https://console.plivo.com/accounts/register/>.
2. From your Plivo account, collect the following information:
 - Authentication ID
 - Authentication token
 - Phone number





The first screenshot shows the Plivo account details page. It includes fields for AUTH ID, AUTH TOKEN, and ACCOUNT TYPE. The AUTH ID and AUTH TOKEN are highlighted with blue boxes and labeled 'Authentication ID' and 'Authentication Token' respectively.

The second screenshot shows the Plivo 'Numbers' page. It displays a table of phone numbers. One number is highlighted with a blue box and labeled 'Phone Number'.


NUMBER & ALIAS	AREA	TYPE	VOICE RATE/MIN	SMS RATE/MSG	MONTHLY FEE	APP TYPE	APPLICATION	STATUS	VERIFICATION
[Redacted]	Ohio	Fixed	\$ 0.0085	\$ 0.0000	\$ 0.8000	XML	Demo Speak	Active	-

3. Log in to Versa Director.
4. Select the Administration tab in the top menu bar.
5. Select Notification Configuration > SMS in the left menu bar. Note that in earlier releases, you could configure SMTP and SMS notifications on a single screen.



6. In the SMS Configuration pane, click the  Edit icon. In the Add SMS Configuration popup window, enter information for the following fields.

Field	Description
Enable SMS Configuration	Click to enable SMS.
Provider (Required)	Enter Plivo as the SMS service provider name.
Phone Number (Required)	Enter the phone number that you received from the SMS service provider.
Auth ID (Required)	Enter the authentication ID that you received from the SMS service provider.
Auth Token	Enter the authentication token that you received from the SMS service provider.


7. Click OK.
8. Review the field values in the SMS Configuration pane to confirm that they are correct. If they are not, click the .

https://docs.versa-networks.com/Management_and_Orchestration/Versa_Director/Configuration/Enable_SMS_Text_Messaging

Updated: Thu, 24 Oct 2024 10:44:44 GMT

Copyright © 2024, Versa Networks, Inc.

Edit icon, enter the correct values, and then click OK.



Supported Software Information

Releases 20.2 and later support all content described in this article, except:

- In Release 22.1.3, the SMTP and SMS notification configurations no longer appear on the same screen. There are now separate SMTP and SMS notification configuration screens.

Additional Information

[Configure Notifications for Alarms](#)

[Configure SMTP Notifications](#)

[Configure Webhook Notifications for Alarms](#)