




INSTALLATION + QUICK START GUIDE FOR FPCV2:

- 1) DOWNLOAD THE FPCV2CLIENT INSTALLER FROM [HERE](#). ENSURE THE MICROSOFT VC++ 2015 REDISTRIBUTABLE IS INSTALLED ON YOUR MACHINE. IF NOT GET IT [HERE](#) AND [HERE](#). (YOU PROBABLY NEED BOTH).
- 2) UNINSTALL ANY PREVIOUS VERSIONS OF FPCV2CLIENT FROM "ADD OR REMOVE PROGRAMS" IN WINDOWS SETTINGS.
- 3) RUN THE INSTALLER.
- 4) DOUBLE CLICK THE SHORTCUT FOR FPCV2CLIENT ON YOUR DESKTOP.
- 5) IN THE MAIN FPC WINDOW, CLICK CONNECT. THIS WILL LAUNCH THE FPC/DIGISTRIPS DISCORD OAUTH LOGIN.



- 6) LOGIN WITH YOUR DISCORD CREDENTIALS. LOGIN MAY BE (SECURELY) CACHED ON YOUR LOCAL MACHINE, SO YOU MAY NOT HAVE TO FILL THIS INFORMATION IN EVERY TIME.
- 7) AFTER LOGGING IN YOU SHOULD ARRIVE AT THE ATC SETTINGS PAGE.
 - A) FOR **DEL/GND/TWR/APP POSITIONS**, FILL OUT THE FORM. MAKE SURE YOUR DISCORD AIRPORT SECTOR CORRELATES TO THE ONE YOU WILL OCCUPY IN DISCORD.

ATC Settings Center

Please fill out the settings below.


Airport ICAO:
 ✓

Position:
 ✓


Discord Airport:
 ✓

Continue →

B) FOR CTR, CLICK THE BLUE "CENTER" BUTTON AT THE TOP OF THE PAGE. SELECT YOUR ARTCC AND DISCORD SECTOR. CURRENTLY ONLY US ARTCCS ARE LOADED, BUT OTHERS WILL BE SHORTLY.

A dark-themed dialog box titled "Center Controller" with a close button (X) in the top right corner. It contains two dropdown menus. The first is labeled "ARTCC:" and has a placeholder text "Select one...". The second is labeled "Discord Sector:" and also has a placeholder text "Select one...". At the bottom right, there is a green button labeled "Continue" with a right-pointing arrow.

8) CLICK CONTINUE. IF SUCCESSFUL, YOU WILL RECEIVE THE FOLLOWING MESSAGE. **MAKE SURE TO NOTE YOUR VRC CALLSIGN!!!**



9) CLICK OK.

A) FOR VRC, CLICK FILE → CONNECT... **ENSURE YOUR CALLSIGN IS THE EXACT SAME AS THE ONE FROM THE PREVIOUS STEP!** ENSURE THAT THE REST OF THE FIELDS ARE FILLED OUT WITH ANY ALPHANUMERIC CHARACTERS. ENSURE THAT FACILITY AND RATING ARE **HIGHER THAN OBSERVER**. ENSURE THAT SERVER IS **LOCALHOST!** CLICK "CONNECT".

B) FOR EUROSCOPE, CLICK THE CONNECT BUTTON. ENSURE THE SAME FIELDS ARE FILLED OUT AS PREVIOUSLY MENTIONED. ENSURE THAT THE "CONNECT TO VATSIM" BOX **IS CHECKED**. TYPE "**LOCALHOST**" IN THE SERVER FIELD. CLICK "CONNECT".

10) IF YOU HAVE SUCCESSFULLY CONNECTED, YOU WILL SEE "CONNECTED TO SERVER" AT THE TOP OF VRC, "CONNECTED!" IN THE FPC DEBUG WINDOW, AND "KDEN_TWR CONNECTED!" (EXCEPT YOUR POSITION) IN THE FPC MAIN WINDOW. YOU MAY NOW USE VRC/EUROSCOPE AS USUAL.

HAPPY CONTROLLING!