


DERECK LAM HON WAH

3rd Year BSc. Computer Science (System Engineering)
Student from Middlesex University Mauritius



Dereck Lam Hon Wah



derecklhw



DISCLAIMER



UNDERSTANDING THE BOOT PROCESS

OVERVIEW OF THE BOOT PROCESS

BIOS

MBR

GRUB

KERNEL


SYSTEMD

RUNLEVEL

BIOS

BASIC INPUT OUTPUT SYSTEM


- Run from **ROM** and **INDEPENDENT** from the OS.
- Perform the **POST** (Power-on self-test).
- Searches, loads, and executes the MBR to boot the OS.



MBR

MASTER BOOT RECORD


- Responsible for loading and executing the **boot loader**.
- Located in the **1st** sector of the boot device.
- Is **512 bytes** in size.
- Contains the **boot loader** program and informations about the disk partitions.



GRUB


GRAND UNIFIED BOOTLOADER

- **LILO** (Linux Loader) in old system.
- A splash screen with various functionalities.
- **GRUB** configuration file is located **/boot/grub/** by default.
- Insert the kernel into memory.



KERNEL

- **Core** of the OS and has **total** control over the computer resources.
- Follow predefined procedures:
 - a. decompress itself in place (**vmlinux** vs **vmlinux**).
 - b. Mounts the root file system as specified in the **grub.conf**.
 - c. run the **init process**.



SYSTEMD

PID 1

- The parent process initiated by the **kernel's init process**.
- Previously known as **SysVinit** process.
- Performs a range of tasks:
 - a. probe all remaining hardware
 - b. mount filesystems
 - c. initiate and terminate services
 - d. manage essential system processes like user login
 - e. run a desktop environment
- Lastly, decide the **target** or **state** the linux system boots into.

RUNLEVEL

CURRENT STATE OF THE OS

- Defining which system services are running.
- Previously, **SysVinit** identified run levels by number.
- However, **.target files** now replace run levels in **Systemd**.

poweroff.target	run level 0	turn off (shut down) the computer
rescue.target	run level 1	initiate a rescue shell process
multi-user.target	run level 3	configure the system as a non-graphical (console) multi-user environment
graphical.target	run level 5	establish a graphical multi-user interface with network services
reboot.target	run level 6	restart the machine

RUNLEVEL

Let's check our default target:

```
$ sudo systemctl get-default
```

To change boot target :

```
$ sudo systemctl set-default <target>
```

To change the target while the system runs.

```
$ sudo systemctl isolate <target>
```