

## **Steps To run when staring with Zosconnect.**

**(Only when we are doing setup for the first time)**

PDS - IBMUSER.SVSC.CONFIG

1) Run the job \$RACFCM1 job 3 times by changing control members

- a) ZCONRAC1 - Define Initial RACF
- b) ZCONCERT - Define Certificates
- c) ZCONLIST - LIST Certificate Info.

2) Run the job ZOSCOWNS to change owner to the /var/zosconnect Directories.

## **FOR REGULAR SERVER START**

**IN LOG (ISPF→SD→LOG)**

- 1) Start Angle server - /S ZOSCAGL
- 2) Start Z/OS server - /S ZOSCSRV
- 3) Start Demon server - /S RSED
- 4) CICS START - /S CICSTS53,START=INITIAL

## **IN CICS REGION (TO SETUP THE PROGRAM DETAILS)**

1) Install BBOA

CEDA INSTALL GROUP(BBOACSD)

2) Add Group

CEDA ADD GROUP(BBOACSD) LIST(BBOLIST)

3) Start BBOA

BBOC START\_TRUE

4) Start WOLA server

BBOC START\_SRVR RGN=ZCONNREG DGN=GROUP NDN=NAME2 SVN=NAME3 SVC=\* MNC=1 MXC=10  
TXN=N SEC=N REU=Y

5) Install Library & Application program

CEDA INSTALL GROUP(LOANGRP) LIB(LOANLIB)

CEDA INSTALL GROUP(LOANGRP) PROG(LOANAPPO)

6) Install file

CEDA INSTALL FILE(CUSTMAST) GROUP(LOANGRP)

CEMT SET FILE(CUSTMAST) OPEN

### **FOR REGULAR SERVER STOP IN LOG(ISPF→SD→LOG)**

- 1) CICS STOP - /F CICSTS53,CEMT P SHUT IMM
- 2) Stop Demon server - /P RSED
- 3) Stop Z/OS server - /P ZOOSCRV
- 4) Stop Angle server - /P ZOSCAGL