

partition

[TS-WXL](#)

View HDD partitions

View with fdisk

```
-sh-3.2 $ fdisk / dev / sda
-sh: fdisk: command not found
-sh-3.2$ /sbin/!!
/sbin/fdisk /dev/sda
You will not be able to write the partition table
```

The number of cylinders for this disk is set to 60801.
 There is nothing wrong with that, but this is larger than 1024,
 and could in certain setups cause problems with:

- 1) software that runs at boot time (e.g., old versions of LILO)
- 2) booting and partitioning software from other OSs
 (eg, DOS FDISK, OS / 2 FDISK)

Command (m for help): p

```
Disk /dev/sda: 500.1 GB, 500107862016 bytes
255 heads, 63 sectors/track, 60801 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
```

Device	Boot	Start	End	Blocks	Id	System
/ dev / sda1	1	60802	488386583+	ee	EFI	GPT

Command (m for help): q

-sh-3.2\$

After all GPT

Watch with parted

```
-sh-3.2$ /usr/local/sbin/parted -s /dev/sda print
Warning: Unable to open /dev/sda read-write (Permission denied). /dev/sda has been opened read-only.
Warning: Unable to open /dev/sda read-write (Permission denied). /dev/sda has been opened read-only.
Model: SAMSUNG HD502HI (scsi)
Disk /dev/sda: 500GB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
```

Number	Start	End	Size	File system	Name	Flags
1	17.4kB	1024MB	1024MB	ext3	primary	
2	1024MB	6144MB	5120MB	ext3	primary	
3	6144MB	6144MB	512B		primary	
4	6144MB	6144MB	512B		primary	
5	6144MB	7168MB	1024MB	linux-swap	primary	
6	7168MB	492GB	485GB	xfs	primary	

-sh-3.2\$

Sda2 is ext3 (LS-XHL is xfs)



TS-WXL

[Rakuten Ichiba](#)
[Amazon](#)
[Yahoo Shopping](#)
[Livedoor Department Store](#)

[←
straight forward](#)

[Hack of record](#)
[LinkStation / KuroBox trying to
hack](#)

[→
Go straight \(2\)](#)

ツイート

@yasunari_yさんへツイートする

@yasunari_yさんをフォロー

Copyright (C) 2003-2013 Yasunari Yamashita. All Rights Reserved. [Yasunari](#)
yama yamasita.jp [Yasunari Yamashita](#) 向 Mukoichi, Kyoto