

DEVICE=eth0

```
cd /etc/sysconfig/network-scripts/  
ls
```

```
vi ifcfg-eth0
```

增添以下内容：

```
DEVICE=eth0          #设备类型，网卡名称  
HWADDR=00:50:56:ab:7e:c0    #MAC地址  
TYPE=Ethernet         #网络类型  
UUID=ca65bd94-b921-4f5c-b02e-6e1a6141b9d0  #  
ONBOOT=yes           #开机启动  
NM_CONTROLLED=yes       #  
BOOTPROTO=none        #协议，静态，动态，无  
IPADDR=192.168.200.33     #IP地址  
NETMASK=255.255.255.0     #子网掩码  
GATEWAY=192.168.200.1     #网关  
DNS1=114.114.114.114     #第一个域名解析服务器  
IPV6INIT=no           #是否使用IPV6地址  
USERCTL=no            #是否允许非root用户控制该设备
```

```
service network restart
```

或

```
/etc/init.d/network reload
```

```
ifdown eth0 #关闭网络
```

```
ifup eth0   #启动网络
```

eg：

```
[root@localhost ~]# cd /etc/sysconfig/net
```

```
netconsole      network      networking/      network-scripts/
```

```
[root@localhost ~]# cd /etc/sysconfig/network-scripts/
```

```
[root@localhost network-scripts]# ls
```

```
ifcfg-eth0  ifdown      ifdown-eth  ifdown-ipv6  ifdown-post  ifdown-routes  ifdown-tunnel  ifup-aliases  ifup-eth  ifup-ipv6
```

```
ifup-plip  ifup-post  ifup-routes  ifup-tunnel  init.ipv6-global  network-functions
```

```
ifcfg-lo   ifdown-bnep  ifdown-ipp  ifdown-isdn  ifdown-ppp  ifdown-sit  ifup          ifup-bnep  ifup-ipp  ifup-isdn
```

```
ifup-plusb  ifup-ppp  ifup-sit  ifup-wireless  net.hotplug      network-functions-ipv6
```

```
[root@localhost network-scripts]# cat ifcfg-eth0
```

```
DEVICE=eth0
```

```
HWADDR=00:0C:29:18:18:0C
```

```
TYPE=Ethernet
```

```
UUID=2f91ddfc-9e0c-4ba1-bda4-6f121ea5ba21
```

```
#ONBOOT=no
```

```
ONBOOT=yes
```

```
NM_CONTROLLED=yes
```

```
#BOOTPROTO=dhcp
```

```
BOOTPROTO=none
```

```
IPADDR=192.168.123.150
```

```
NETMASK=255.255.255.0
```

```
GATEWAY=192.168.123.1
```

```
DNS1=114.114.114.114
```

```
IPV6INIT=no
```

```
USERCTL=no
```

```
[root@localhost network-scripts]#
```

```
[root@localhost network-scripts]#
```

```
[root@localhost network-scripts]# service network
```

```
Usage: /etc/init.d/network {start|stop|status|restart|reload|force-reload}
```

```
[root@localhost network-scripts]# /etc/init.d/network
```

Usage: /etc/init.d/network {start|stop|status|restart|reload|force-reload}