

UF_ROUTE_bend_radius_method_e [\(view source\)](#)

Defined in: `uf_route.h`

Also known as:

- `UF_ROUTE_bend_radius_method_t`
- `UF_ROUTE_bend_radius_method_p_t`

Overview

Bend corner creation methods.

Data Members

`UF_ROUTE_bend_radius_method_radius`

`UF_ROUTE_bend_radius_method_ratio_to_diameter`

`UF_ROUTE_bend_radius_method_bend_radius_table`

`UF_ROUTE_bend_radius_method_inner_radius`

UF_ROUTE_branch_path_numbering_sequence_method_e [\(view source\)](#)

Defined in: `uf_route.h`

Also known as:

- `UF_ROUTE_branch_path_numbering_sequence_method_t`
- `UF_ROUTE_branch_path_numbering_sequence_method_p_t`

Overview

Used by the Branch Path Numbering plugin.

See `UFD_Routing_BranchPathNumbering.cxx` for an example plugin.

Data Members

`UF_ROUTE_branch_path_numbering_sequence_numbers`
1, 2, 3,.....

`UF_ROUTE_branch_path_numbering_sequence_upper_case`
A, B, C,.....

`UF_ROUTE_branch_path_numbering_sequence_lower_case`
a, b, c,.....

UF_ROUTE_duct_calculator_errors_e [\(view source\)](#)

Defined in: `uf_route.h`

Also known as:

- `UF_ROUTE_duct_calculator_errors_t`
- `UF_ROUTE_duct_calculator_errors_p_t`

Overview

The duct size calculator plugins use this enumeration to tell the duct size calculator dialog about any errors that may occur in a plugin.

Data Members

`UF_ROUTE_DUCT_ERROR_OK = 0`

No errors.

`UF_ROUTE_DUCT_NO_PLUGIN_FOUND`

Cannot find the plugin. Verify the plugin configuration in the application view file.

`UF_ROUTE_DUCT_CANT_CALCULATE`

Cannot calculate all of the values given the input parameters.

`UF_ROUTE_duct_parameter_types_e` ([view source](#))

Defined in: `uf_route.h`

Also known as:

- `UF_ROUTE_duct_parameter_types_t`
- `UF_ROUTE_duct_parameter_types_p_t`

Overview

The duct size calculator dialog uses this enumeration to tell the plugin which parameter the dialog is sending to the plugin. The plugin should then calculate the value for this parameter.

Data Members

`UF_ROUTE_DUCT_HEIGHT`

maps to the height parameter of the duct

`UF_ROUTE_DUCT_WIDTH`

maps to the width parameter of the duct

`UF_ROUTE_DUCT_ASPECTRATIO`

maps to the Aspect ratio of the duct

`UF_ROUTE_DUCT_EQUIVALENT_DIAMETER`

maps to the equivalent diameter of the rectangular or flat oval duct

`UF_ROUTE_DUCT_DIAMETER`

maps to the diameter of the circular duct

`UF_ROUTE_DUCT_AREA`

maps to the area parameter of the duct

`UF_ROUTE_DUCT_VELOCITY`

maps to the velocity parameter of the duct

UF_ROUTE_DUCT_VOLFLOWRATE

maps to the volume flow rate parameter of the duct

UF_ROUTE_DUCT_SHAPE_CHANGE

This enum member indicates that the user has changed the shape, so the parameters needs to be recalculated

UF_ROUTE_DUCT_DEFAULT

If no parameter is defined, default calculations will be done.

UF_ROUTE_duct_reinforcement_types_e ([view source](#))

Defined in: `uf_route.h`

Also known as:

- `UF_ROUTE_duct_reinforcement_types_t`
- `UF_ROUTE_duct_reinforcement_types_p_t`

Overview

The plugin for Duct Reinforcement uses this enumeration to tell the dialog the type of reinforcement to create

Data Members**UF_ROUTE_DUCT_REINFORCEMENT_TYPE_NONE**

No reinforcement needs to be created on the selected duct

UF_ROUTE_DUCT_REINFORCEMENT_TYPE_INSIDE

Inside reinforcement needs to be created on the selected duct

UF_ROUTE_DUCT_REINFORCEMENT_TYPE_OUTSIDE

Outside reinforcement needs to be created on the selected duct

UF_ROUTE_duct_segment_attribute_status_e ([view source](#))

Defined in: `uf_route.h`

Also known as:

- `UF_ROUTE_duct_segment_attribute_status_t`
- `UF_ROUTE_duct_segment_attribute_status_p_t`

Overview

The duct size calculator plugins use this enumeration to tell the duct size calculator dialog about the attributes on the selected segments.

Data Members**UF_ROUTE_DUCT_EMPTY_ATTRIBUTES**

None of the selected segments have attributes.

UF_ROUTE_DUCT_ATTRIBUTES_NOT_EQUAL

The selected segments have attributes whose values don't match.

UF_ROUTE_DUCT_VALID_ATTRIBUTES

All of the selected segments have valid attributes.

UF_ROUTE_duct_shape_e [\(view source\)](#)

Defined in: `uf_route.h`

Also known as:

- `UF_ROUTE_duct_shape_t`
- `UF_ROUTE_duct_shape_p_t`

Overview

The duct size calculator dialog use this enumeration to tell the duct size calculator plugin the shape of the duct being calculated.

Data Members

`UF_ROUTE_DUCT_RECTANGULAR`

`UF_ROUTE_DUCT_CIRCULAR`

`UF_ROUTE_DUCT_FLATOVAL`
