



**PLATFORM SETUP GUIDES / Access management / default-roles**

# Contents

- [PLATFORM SETUP GUIDES / Access management / Default roles](#)

## PLATFORM SETUP GUIDES / Access management / Default roles

Below you can find the list of all the default roles that you can add or import into the Identity and Access Management solution to properly manage the access to all the FLOWX.AI microservices.

### Default roles

A complete list of all the default roles based on modules (access scope):

Module	Scopes	Role default value
manage-platform	read	ROLE_ADMIN_MANAGE_PLATFORM_READ
manage-platform	admin	ROLE_ADMIN_MANAGE_PLATFORM_ADMIN
manage-processes	import	ROLE_ADMIN_MANAGE_PROCESS_IMPORT
manage-processes	read	ROLE_ADMIN_MANAGE_PROCESS_READ

Module	Scopes	Role default value
manage-processes	edit	ROLE_ADMIN_MANAGE_PROCESS_EDIT
manage-processes	admin	ROLE_ADMIN_MANAGE_PROCESS_ADMIN
manage-integrations	admin	ROLE_ADMIN_MANAGE_INTEGRATIONS_ADMIN
manage-integrations	read	ROLE_ADMIN_MANAGE_INTEGRATIONS_READ
manage-integrations	edit	ROLE_ADMIN_MANAGE_INTEGRATIONS_EDIT
manage-integrations	import	ROLE_ADMIN_MANAGE_INTEGRATIONS_IMPORT
manage-configurations	import	ROLE_ADMIN_MANAGE_CONFIG_IMPORT
manage-configurations	read	ROLE_ADMIN_MANAGE_CONFIG_READ
manage-configurations	edit	ROLE_ADMIN_MANAGE_CONFIG_EDIT

Module	Scopes	Role default value
manage-configurations	admin	ROLE_ADMIN_MANAGE_CONFIG_ADMIN
manage-users	read	ROLE_ADMIN_MANAGE_USERS_READ
manage-users	edit	ROLE_ADMIN_MANAGE_USERS_EDIT
manage-users	admin	ROLE_ADMIN_MANAGE_USERS_ADMIN
manage-processes	edit	ROLE_ENGINE_MANAGE_PROCESS_EDIT
manage-processes	admin	ROLE_ENGINE_MANAGE_PROCESS_ADMIN
manage-instances	read	ROLE_ENGINE_MANAGE_INSTANCE_READ
manage-instances	admin	ROLE_ENGINE_MANAGE_INSTANCE_ADMIN
manage-licenses	read	ROLE_LICENSE_MANAGE_READ

Module	Scopes	Role default value
manage-licenses	edit	ROLE_LICENSE_MANAGE_EDIT
manage-licenses	admin	ROLE_LICENSE_MANAGE_ADMIN
manage-contents	import	ROLE_CMS_CONTENT_IMPORT
manage-contents	read	ROLE_CMS_CONTENT_READ
manage-contents	edit	ROLE_CMS_CONTENT_EDIT
manage-contents	admin	ROLE_CMS_CONTENT_ADMIN
manage-media-library	import	ROLE_MEDIA_LIBRARY_IMPORT
manage-media-library	read	ROLE_MEDIA_LIBRARY_READ
manage-media-library	edit	ROLE_MEDIA_LIBRARY_EDIT

Module	Scopes	Role default value
manage-media-library	admin	ROLE_MEDIA_LIBRARY_ADMIN
manage-taxonomies	import	ROLE_CMS_TAXONOMIES_IMPORT
manage-taxonomies	read	ROLE_CMS_TAXONOMIES_READ
manage-taxonomies	edit	ROLE_CMS_TAXONOMIES_EDIT
manage-taxonomies	admin	ROLE_CMS_TAXONOMIES_ADMIN
manage-tasks	read	ROLE_TASK_MANAGER_TASKS_READ
manage-hooks	import	ROLE_TASK_MANAGER_HOOKS_IMPORT
manage-hooks	read	ROLE_TASK_MANAGER_HOOKS_READ
manage-hooks	edit	ROLE_TASK_MANAGER_HOOKS_EDIT

Module	Scopes	Role default value
manage-hooks	admin	ROLE_TASK_MANAGER_HOOKS_ADMIN
manage-process-allocation-settings	import	ROLE_TASK_MANAGER_PROCESS_ALLOCATION
manage-process-allocation-settings	read	ROLE_TASK_MANAGER_PROCESS_ALLOCATION
manage-process-allocation-settings	edit	ROLE_TASK_MANAGER_PROCESS_ALLOCATION
manage-process-allocation-settings	admin	ROLE_TASK_MANAGER_PROCESS_ALLOCATION
manage-out-of-office-users	import	ROLE_TASK_MANAGER_OOO_IMPORT

Module	Scopes	Role default value
manage-out-of-office-users	read	ROLE_TASK_MANAGER_OOO_READ
manage-out-of-office-users	edit	ROLE_TASK_MANAGER_OOO_EDIT
manage-out-of-office-users	admin	ROLE_TASK_MANAGER_OOO_ADMIN
manage-notification-templates	import	ROLE_NOTIFICATION_TEMPLATES_IMPORT
manage-notification-templates	read	ROLE_NOTIFICATION_TEMPLATES_READ
manage-notification-templates	edit	ROLE_NOTIFICATION_TEMPLATES_EDIT



Module	Scopes	Role default value
manage-notification-templates	admin	ROLE_NOTIFICATION_TEMPLATES_ADMIN
manage-notifications	import	ROLE_MANAGE_NOTIFICATIONS_IMPORT
manage-notifications	read	ROLE_MANAGE_NOTIFICATIONS_READ
manage-notifications	edit	ROLE_MANAGE_NOTIFICATIONS_EDIT
manage-notifications	admin	ROLE_MANAGE_NOTIFICATIONS_ADMIN
manage-document-templates	import	ROLE_DOCUMENT_TEMPLATES_IMPORT
manage-document-templates	read	ROLE_DOCUMENT_TEMPLATES_READ

Module	Scopes	Role default value
manage-document-templates	edit	ROLE_DOCUMENT_TEMPLATES_EDIT
manage-document-templates	admin	ROLE_DOCUMENT_TEMPLATES_ADMIN

## Importing roles

### ! INFO

You can import a super admin group and its default roles in Keycloak using the following script file.

### ! DOWNLOAD THE SCRIPT + ROLES:

#### Import Script

You need to edit the following script parameters:

- `baseAuthUrl`
- `username`
- `password`
- `realm`
- `the name of the group for super admins`

The requests package is needed in order to run the script. It can be installed with the following command:

```
pip3 install requests
```

The script can be run with the following command:

```
python3 importUsers.py
```

**Was this page helpful?**