

🏠 PowerSploit

Search docs

Home

Recon

About

Functions

Export-PowerViewCSV

Resolve-IPAddress

ConvertTo-SID

ConvertFrom-SID

Convert-ADName

ConvertFrom-UACValue

Add-RemoteConnection

Remove-RemoteConnection

Invoke-UserImpersonation

Invoke-RevertToSelf

Get-DomainSPNTicket

Invoke-Kerberoast

Get-PathAcl

Get-DomainDNSZone

Get-DomainDNSRecord

Get-Domain

Get-DomainController

Get-Forest

Get-ForestDomain

Get-ForestGlobalCatalog

Find-DomainObjectPropertyOutlier

Get-DomainUser

New-DomainUser

Set-DomainUserPassword

Get-DomainUserEvent

Get-DomainComputer

Get-DomainObject

Set-DomainObject

Set-DomainObjectOwner

Get-DomainObjectAcl

Add-DomainObjectAcl

Find-InterestingDomainAcl

Get-DomainOU

Get-DomainSite

Get-DomainSubnet

Get-DomainSID

Get-DomainGroup

New-DomainGroup

Get-DomainManagedSecurityGroup

Get-DomainGroupMember

Add-DomainGroupMember

Get-DomainFileServer

Get-DomainDFSShare

Get-DomainGPO

Get-DomainGPOLocalGroup



This is the latest development version
Some features may not yet be available in the published stable version. Read the [stable version of this documentation](#).

Install-SSP

SYNOPSIS

Installs a security support provider (SSP) dll.

Author: Matthew Graeber (@mattifestation)

License: BSD 3-Clause

Required Dependencies: None

Optional Dependencies: None

SYNTAX

```
Install-SSP [[-Path] <String>]
```

DESCRIPTION

Install-SSP installs an SSP dll. Installation involves copying the dll to %windir%\System32 and adding the name of the dll to HKLM\SYSTEM\CurrentControlSet\Control\Lsa\Security Packages.

EXAMPLES

----- EXAMPLE 1 -----

```
Install-SSP -Path .\mimilib.dll
```

PARAMETERS

-Path

{{Fill Path Description}}

Type: **String**
Parameter Sets: (All)
Aliases:

Required: **False**
Position: **1**
Default value: **None**
Accept pipeline input: **False**
Accept wildcard characters: **False**

INPUTS

OUTPUTS

NOTES

The SSP dll must match the OS architecture. i.e. You must have a 64-bit SSP dll if you are running a 64-bit OS. In order for the SSP dll to be loaded properly into lsass, the dll must export SpLsaModelInitialize.

RELATED LINKS

⬅ Previous

Next ➡

Built with [MkDocs](#) using a [theme](#) provided by [Read the Docs](#).

  latest