

# getcap(8) — Linux manual page

[NAME](#) | [SYNOPSIS](#) | [DESCRIPTION](#) | [OPTIONS](#) | [REPORTING BUGS](#) | [SEE ALSO](#) | [COLOPHON](#)

 Search online pages**GETCAP(8)**

System Manager's Manual

**GETCAP(8)**

## NAME [top](#)

getcap - examine file capabilities

## SYNOPSIS [top](#)

**getcap** [-v] [-n] [-r] [-h] *filename* [ ... ]

## DESCRIPTION [top](#)

**getcap** displays the name and capabilities of each specified file.

## OPTIONS [top](#)

- h** prints quick usage.
- n** prints any non-zero user namespace root user ID value found to be associated with a file's capabilities.
- r** enables recursive search.
- v** display all searched entries, even if the have no file-capabilities.

NOTE: an *empty* value of '=' is **not** equivalent to an omitted (or removed) capability on a file. This is most significant with respect to the Ambient capability vector, since a process with Ambient capabilities will lose them when executing a file having '=' capabilities, but will retain the Ambient inheritance of privilege when executing a file with an omitted file capability.

This special *empty* setting can be used to prevent a binary from executing with privilege. For some time, the kernel honored this suppression for root executing the file, but the kernel developers decided after a number of years that this behavior was unexpected for the superuser and reverted it just for that user identity. Suppression of root privilege, for a process tree, is possible, using the [capsh\(1\)](#) **--mode** option.

*filename*

One file per line.

## REPORTING BUGS [top](#)

Please report bugs via:

[https://bugzilla.kernel.org/buglist.cgi?component=libcap&list\\_id=1090757](https://bugzilla.kernel.org/buglist.cgi?component=libcap&list_id=1090757)

## SEE ALSO [top](#)

[capsh\(1\)](#), [cap\\_get\\_file\(3\)](#), [cap\\_to\\_text\(3\)](#), [capabilities\(7\)](#), [user\\_namespaces\(7\)](#), [cmtree\(8\)](#), [getpcaps\(8\)](#) and [setcap\(8\)](#).

## COLOPHON [top](#)

This page is part of the *libcap* (capabilities commands and library) project. Information about the project can be found at <https://git.kernel.org/pub/scm/libs/libcap/libcap.git/>. If you have a bug report for this manual page, send it to [morgan@kernel.org](mailto:morgan@kernel.org) (please put "libcap" in the Subject line). This page was obtained from the project's upstream Git repository <https://git.kernel.org/pub/scm/libs/libcap/libcap.git/> on 2024-06-14. (At that time, the date of the most recent commit that was found in the repository was 2024-05-18.) If you discover any rendering problems in this HTML version of the page, or you believe there is a better or more up-to-date source for the page, or you have corrections or improvements to the information in this COLOPHON (which is *not* part of the original manual page), send a mail to [man-pages@man7.org](mailto:man-pages@man7.org)

2021-08-29

**GETCAP(8)**

---

Pages that refer to this page: [capsh\(1\)](#), [libcap\(3\)](#), [capabilities\(7\)](#), [getpcaps\(8\)](#), [setcap\(8\)](#)

---

HTML rendering created 2024-06-26 by [Michael Kerrisk](#), author of *[The Linux Programming Interface](#)*.

For details of in-depth **Linux/UNIX system programming training courses** that I teach, look [here](#).

Hosting by [jambit GmbH](#).

