


OUTPUT :-



```
--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: no
Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int
% Incomplete command.
Router(config)#interface gi
% Incomplete command.
Router(config)#interface gigabitEthernet 0/0
Router(config-if)#ip add
% Incomplete command.
Router(config-if)#ip address 192.168.0.1 255.255.255.0
Router(config-if)#no shut
Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#ip dhcp
% Incomplete command.
Router(config)#ip dhcp poo
% Incomplete command.
Router(config)#ip dhcp pool ABC-POOL
```

```
Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
Router(config-if)#
Router(config-if)#exit
Router(config)#ip dhcp
% Incomplete command.
Router(config)#ip dhcp poo
% Incomplete command.
Router(config)#ip dhcp pool ABC-POOL
Router(dhcp-config)#network 192.168.0.0 255.255.255.0
Router(dhcp-config)#default
% Incomplete command.
Router(dhcp-config)#default-router 192.168.0.254
% Invalid input detected at '^' marker.
Router(dhcp-config)#default-router 192.168.0.254
Router(dhcp-config)#dns
% Incomplete command.
Router(dhcp-config)#dns
% Incomplete command.
Router(dhcp-config)#dns-server 192.168.0.1
Router(dhcp-config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#write memory
Building configuration...
[OK]
Router#
Router#
```

