







Class/Interface

ZCL_GW_MODEL

Implemented / Active

Proper...

Interfaces

Friends

Attributes

Metho...

Events

Types

Aliases

☐ Parameter

 Exception



























Method

Level

Visibility

M...

Description

CONSTRUCTOR

Instance

Public



CONSTRUCTOR

GET_ABAP_FIELD_NAME

Instance

Public

GET_SORTABLE_ABAP_FIELD_NAME

Instance

Public

GET_FILTERABLE_ABAP_FIELD_NAME

Instance

Public

GET_ENTITY_PROPERTIES

Instance

Private

GET_PROPERTY

Instance

Private



METHOD constructor.


DATA: lr_facade TYPE REF TO /iwbep/cl_mgw_dp_facade.

lr_facade ?= runtime->get_dp_facade().

mpc ?= lr_facade->/iwbep/if_mgw_dp_int_facade~get_model().

ENDMETHOD.

ZCL_GW_MODEL

Class/Interface		ZCL_GW_MODEL		Implemented / Active											
Proper...		Interfaces		Friends		Attributes		Metho...		Events		Types		Aliases	
Parameter		Exception													
Method		Level		Visibility		M...		Description							
CONSTRUCTOR		Instance		Public				CONSTRUCTOR							
GET_ABAP_FIELD_NAME		Instance		Public											

GET_SORTAB... **METHOD** constructor.

GET_FILTERE

GET_ENTITY

GET_PROPERT

```
DATA: lr_facade TYPE REF TO /iwbep/cl_mgw_dp_facade.
```

```
lr_facade ?= runtime->get_dp_facade( ).
```

```
mpc ?= lr_facade->/iwbep/if_mgw_dp_int_facade~get_model( ).
```

```
ENDMETHOD.
```


DPC->GET_MODEL

Class Builder: Class ZCL_DEMO_DPC_EXT Display

Navigation icons: Back, Forward, Search, etc. | Pattern | Pretty Printer | Signature

Ty.	Parameter	Type spec.	Descript.
	value(MODEL)	TYPE REF TO ZCL_GW_MODEL	
	/IWBEP/CX_MGW_TECH_EXCEPTION		

Method: GET_MODEL

```
1  METHOD get_model.  
2  
3  IF me->model IS NOT BOUND.  
4      CREATE OBJECT me->model  
5          EXPORTING  
6              runtime = me.  
7  ENDIF.  
8  
9  model = me->model.  
10  
11 ENDMETHOD.
```