

# BO CLASS SUBCLASS

| Class/Interface     |  | ZCL_DEMO_CUSTOMER_CUST |         | Implemented / Active |          |        |       |             |
|---------------------|--|------------------------|---------|----------------------|----------|--------|-------|-------------|
| Proper...           |  | Interfaces             | Friends | Attributes           | Metho... | Events | Types | Aliases     |
| Parameter           |  | Exception              |         |                      |          |        |       |             |
| Method              |  | Level                  |         | Visibility           |          | M...   |       | Description |
| <ZIF_DEMO_CUSTOMER> |  |                        |         |                      |          |        |       |             |
| GET                 |  | Static M               |         | Public               |          |        |       |             |
| GET_KUNNR           |  | Instance               |         | Public               |          |        |       |             |
| GET_NAME1           |  | Instance               |         | Public               |          |        |       |             |
| GET_STRAS           |  | Instance               |         | Public               |          |        |       |             |
| GET_ORT01           |  | Instance               |         | Public               |          |        |       |             |
| GET_REGIO           |  | Instance               |         | Public               |          |        |       |             |
| GET_REGION_TEXT     |  | Instance               |         | Public               |          |        |       |             |
| GET_PSTLZ           |  | Instance               |         | Public               |          |        |       |             |
| GET_LAND1           |  | Instance               |         | Public               |          |        |       |             |
| GET_LAND_TEXT       |  | Instance               |         | Public               |          |        |       |             |

New methods or  
redefine existing  
methods

# BO CLASS INSTANTIATION

```
METHOD zif_demo_customer~get.
```

```
TRY.
```

```
    DATA(inst) = zif_demo_customer~instances[ node_key = node_key ].
```

```
CATCH cx_sy_itab_line_not_found.
```

```
    inst-node_key = node_key.
```

```
    DATA(class_name) = get_subclass( 'ZCL_DEMO_CUSTOMER' ).
```

```
    CREATE OBJECT inst-instance
```

```
        TYPE (class_name)
```

```
        EXPORTING
```

```
            node_key = inst-node_key.
```

```
    APPEND inst TO zif_demo_customer~instances.
```

```
ENDTRY.
```

```
instance ?= inst-instance.
```

```
ENDMETHOD.
```