


PancakeSwap Sniper Bot Setup Guide

First To set up your sniper you start by adding your wallet information in config.json.

A screenshot of a Notepad window titled 'config - Notepad'. The window shows the content of a config.json file. The file is a JSON object with various configuration parameters for a sniper bot. The parameters include node URL, wallet address, private key, liquidity pool, minimum token received, sell mode, amount in BNB, sell at BNB, stop loss in BNB, amount in BUSD, sell at BUSD, stop loss in BUSD, anti bot, delay blocks, min liquidity, max liquidity, gas price, and gas limit. The status bar at the bottom indicates 'Ln 20, Col 25', '100%', 'Windows (CRLF)', and 'UTF-8'.

```
{
  "NODE": "wss://bsc-ws-node.nariox.org:443",

  "WALLET ADDRESS": "0x58Ca85396133A6579fe78d4778627821085C62d3",
  "PRIVATE KEY": "",

  "LIQUIDITY POOL": "BNB",
  "MINIMUM TOKEN RECIEVED": "0",

  "SELL MODE": "true",
  "AMOUNT IN BNB": "0.0001",
  "SELL AT BNB": "1",
  "STOP LOSS IN BNB": "0",

  "AMOUNT IN BUSD": "100",
  "SELL AT BUSD": "50",
  "STOP LOSS IN BUSD": "5",

  "ANTI BOT": "false",
  "DELAY BLOCKS": "2",

  "MIN LIQUIDITY": "5",
  "MAX LIQUIDITY": "60000000000",
  "GAS PRICE": "7",
  "GAS LIMIT": "2000000"
}
```

“NODE”: To interact with block-chain you use so called JSON-RPC endpoints which we just call nodes. You can set your nodes in this section.

“WALLET ADDRESS”: You enter wallet address that you will be using for sniping

“PRIVATE KEY”: You enter your private key belonging to your sniping wallet.

NOTE: you have to enter your private key and not secret word mnemonic. Here is a tutorial how to get your private key: <https://metamask.zendesk.com/hc/en-us/articles/360015289632-How-to-Export-an-Account-Private-Key>

“LIQUIDITY POOL”: You need to specify the liquidity pool the token is gonna launch on to prevent snipping only the BNB pool but the token has liquidity with BUSD

“MINUMUM TOKEN RECEIVED”: is the minimum token you want to receive on the BNB amount you want to put, the default value to this option is always 0, so if you know the conversion rate, you

can specify an amount, to protect yourself from buying in the top, or when the price is mooned already

"SELL MODE": turn to true, if you want to automatically go in the sell mode after buy, he will sell when he reach the "Sell At BNB" value

"AMOUNT IN BNB": The amount of BNB you want to buy from that token.

"SELL AT BNB": The amount before swap in BNB you want to sell at, for example you bought 1 BNB of a token, and you want to sell it when it reaches 2 BNB before swap.

"STOP LOSS IN BNB": The amount you want to sell at when you're losing money to prevent losing more money, this value is always lower than the "AMOUNT IN BNB", to disable this option just put 0 in it.

"AMOUNT IN BUSD": just like the "AMOUNT IN BNB" but in BUSD, this value works when you switch the "LIQUIDITY POOL" to BUSD.

"SELL AT BUSD": The same as "SELL AT IN BUSD".

"STOP LOSS IN BUSD": The same as "STOP LOSS IN BUSD".

"ANTI BOT": This option is here just to prevent high taxation on the first block or certain blocks when you know a token is having an anti-bot measurement just switch it true and specify the number of blocks you want to skip.

"DELAY BLOCKS": The number of blocks you want to skip.

"MIN LIQUIDITY": This is the minimum liquidity you want to buy a token at.

"MAX LIQUIDITY": This is the maximum liquidity you want to buy a token at.

"GAS PRICE": gas price is the gas price, we advise to use 7 for fair launches, and 5 for already launched tokens.

"GAS LIMIT": gas limit is the gas limit, we advise to use 2000000 for fair launches, and 500000 for already launched tokens.

Execution

```
=====
Welcome To BSNIPER - PancakeSwap Sniper Bot @bsniperbot
=====

Wallet Connected: 0x58Ca85396133A6579fe78d4778627821085C62d3 Buy amount: 0.0001 BNB Sell Target: 1 BNB

Balance: 0.262190703366724201 BNB

1. Normal Snipe
2. Snipe From Telegram
3. Exit
█
```

1. NORMAL SNIPING: When you have to input the token contract address and choose what you want to do in the next coming options
2. Snipe From Telegram: This option if you want to wait for the contract address to be posted on Telegram

```
=====
Welcome To BSNIPER - PancakeSwap Sniper Bot @bsniperbot
=====

Wallet Connected: 0x58Ca85396133A6579fe78d4778627821085C62d3 Buy amount: 0.0001 BNB Sell Target: 1 BNB

Balance: 0.262190703366724201 BNB

1. Normal Snipe
2. Snipe From Telegram
3. Exit
1
Please enter the token you want to buy/sell: 0xe9e7cea3dedca5984780bafc599bd69add087d56
1. Buy
2. Sell
3. Sell with a Target BNB/BUSD balance
4. Exit
█
```

1. Buy: if you want to buy the token
2. Sell: if you want to sell the token
3. Sell With a target BNB/BUSD balance: is when when you want to track the price of token purchased and sell it a target BNB or BUSD balance

```
=====
Welcome To BSNIPER - PancakeSwap Sniper Bot @bsniperbot
=====
```

```
Wallet Connected: 0x58Ca85396133A6579fe78d4778627821085C62d3 Buy amount: 0.0001 BNB Sell Target: 1 BNB
```

```
Balance: 0.262190703366724201 BNB
```

1. Normal Snipe
2. Snipe From Telegram
3. Exit

```
2
```

```
Please enter the Telegram Username: test854254
```

```
Waiting for contract....
```

```
Please enter your phone (or bot token): █
```

When you choose snipe from telegram for the first time you need to enter your linked Telegram phone number, and you will receive a message in your Telegram, you need to enter that code in the bot. This is just for the bot to get the contract address from the telegram channel/group you input earlier, also this is a one time setup

After that the bot will wait for the contract address and buy it from there.

Happy Snipping !!