

## UPS Live Rate- (addon) ( Magento )

### Prerequisites

- **PHP Version Requirement:** PHP 7.3 or higher
- **Magento Version Requirement:** Version 2.3.7 or newer (Tested up to version 2.4.7)
- [Core plug-in](#)
- **firebase/php-jwt**

### Installation Process:

#### 1. Manual Installation:

- Download the ZIP file of the UPS Live Rates addon.
- Extract the contents into your Magento root directory under "app/code".
- Install the "firebase/php-jwt" dependency by following the link:  
<https://github.com/firebase/php-jwt>.
- Run the command: `composer require firebase/php-jwt`.

#### 2. Installation Through Commands:

- Execute the following commands in your terminal or command prompt:

```
php bin/magento setup:upgrade
php bin/magento setup:di:compile
php bin/magento setup:static-content:deploy -f
php bin/magento cache:flush
```

### Settings:

#### 1. Configuring UPS Live Rates:

- Navigate to: Admin> Store> Configuration> Magento UPS> Start Here> Choose the appropriate store view from the store scope.  
<https://prnt.sc/w4uFH7yacQu>
- Add configuration details and connect to the Live Rate service.  
[https://prnt.sc/pqfJXZluQ\\_jH](https://prnt.sc/pqfJXZluQ_jH)

#### 2. Setting Proper Store Address:

- Go to: Admin> System> Settings> Configuration> General> Store Information.
- Ensure the store address is accurately set up.  
<https://prnt.sc/JFY56zX7ffsx>

### 3. Checkout Page - Shipping Methods:

- Once configured, UPS Live Rates options will be available for selection during the checkout process on the shipping methods section.  
[https://prnt.sc/nVJj2hUCj3\\_2](https://prnt.sc/nVJj2hUCj3_2)

## Uninstallation Process

### Manual Process:

- Navigate to the Magento root directory.
- Delete the "**UPS/Liverates**" directory manually from the "app/code" directory.

### Command Line:

- Open your terminal or command prompt.
- Execute the following command:

```
bin/magento module:disable UPS_Liverates
```

- Execute the following command for Uninstall module:

```
bin/magento module:uninstall UPS_Liverates
```

- Then, execute the following commands:

```
php bin/magento setup:upgrade
php bin/magento setup:di:compile
php bin/magento setup:static-content:deploy -f
php bin/magento cache:flush
```

## Reconnection Process

In case of disconnection or reconnection, follow the [Installation Process](#) steps again.

## Functionality of Activating/Deactivating the Plugin

- **Deactivate Connection**
  - Navigate to: Admin > Store > Configuration > Magento UPS > Start Here.
  - Click on "Deactivate Connection" to deactivate the plugin.
- **Activate**
  - To activate the plugin, follow the [Installation Process](#) steps again.

## Exceptions Cases :

- If instance\_id is updated from the file in code and already connected with old instance\_id in that case, the module does not work.
- If modules are removed from app/code or disabled the schema will not be removed from magento 2 database.
- If Core remove without disabled its functionality from app/code in that case Liverates will work, its disabled standard way then Liverates working fine.