


Homework 4



CLI configuration for router 1

```
Router>enable
```

```
Router#conf t
```

Enter configuration commands, one per line. End with CNTL/Z.

```
Router(config)#hostname R!
```

```
R!(config)#hostname R1
```

```
R1(config)#interface fa
```

```
R1(config)#interface fastEthernet 0/0
```

```
R1(config-if)#ip address 192.168.1.10 255.255.255.0
```

```
R1(config-if)#no shutdown
```

```
R1(config-if)#
```

```
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
```

```
R1(config-if)#interface ser
R1(config-if)#interface seri
R1(config-if)#exit
R1(config)#inter
R1(config)#interface ser
R1(config)#interface serial 0/0
R1(config-if)#ip address 192.168.2.1 255.255.255.0
R1(config-if)#clock rate 56000
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#ip route 192.168.3.0 255.255.255.0 192.168.2.2
R1(config)#
```

CLI configuration for router 2

```
Router>enable
```

```
Router#conf t
```

Enter configuration commands, one per line. End with CNTL/Z.

```
Router(config)#hostname R2
```

```
R2(config)#interface fastEthernet 0/0
```

```
R2(config-if)#ip address 192.168.3.10 255.255.255.0
```

```
R2(config-if)#no shutdown
```

```
R2(config-if)#
```

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

R2(config-if)#exit

R2(config)#interface serial 0/0

R2(config-if)#ip address 192.168.2.2 255.255.255.0

R2(config-if)#no shutdown

R2(config-if)#exit

R2(config)#ip route 192.168.1.0 255.255.255.0 192.168.2.1

Ömer Faruk Uysal

19290337