

## <Movie Scene Shortcut>

Play Favorite Scene at One-Click with Zoom, Speed and A-B Repeat saved.

### CAUTION:

+One Shortcut file has only one Scene.

If you want to playback many scenes in one movie in sequence, need to create Shortcut files corresponding to each scene, and playback them as playlist(by Button 'PL' in VideoPlayer enabled.

If you want to control Scene-playback order, rename Shortcut files by ascending name order).

+ Scene saved in Shortcut file is valid only on same phone.

When playing on other phone, you get other Image than you would , because of different screen size and resolution of the other phone(if you not use Zoom or Pan, there is no problem).

+If you move movie file used in Shortcut file, to Other Drive or SD card, link to movie in Shortcut file will not work and playback disabled.

## ----- Creating Shortcut -----

While playbacking movie(also under Paused OK), select 'Create Playback Shortcut' in Combobox.  
'vlnk' extension file created.

\*Using playback by clicking other shortcut will do.

## ----- Playback by Shortcut -----

Shortcut plays the video starting at Time Position when you created shortcut(let video at Pause, recommended on Saving for adjusting video start position to correct).

So if you want to create shortcut playing video from beginning, you need to pause video at time 0:00 and save.

Shortcut with A-B Repeat, starts always at 'A' position.

\*After change speed, then even PAUSEed, changed speed recorded.

+Shortcut File is Created in Current Folder.

+For A-B Repeat, 'B' selection finished, needed (later point in time than A).

CAUTION: Use Under-Playback Frame for Selecting A or B.

Don't use 'PAUSE and push FF or FR button' operation for Selecting: Still Image Remains during pushing FF or FR button, these are NOT Under-Playback Frame( causes Playback error. Confirm repeated scene before File-saving). Instead, Use "Slow"(Select 0.3 etc. as Speed) (and PAUSE where you like), then Select A or B, for selecting more correct position.

+Starting Point Correction Feature on A-B Repeat

In default, Starting Point is corrected from Key frame because it might take around 10 sec to arrive at starting point you selected as A, especially with Slow speed setting.

\*Key frames interval sometimes reaches 10-20 sec. In that case, you have to see not-aimed scene in about 10 sec even in normal speed.

If image distorted at start point (on Low-spec device, etc.), Turn off this feature at video player section in Preference.

\*This feature works only for A-B Repeat, now (Not works on Non-Repeat Shortcut )

+Auto Resize Lock for Video called from shortcut:

If shortcut created under manual Zoomed or Panned, in default Auto-Resize disabled to prevent non-intentional resizing with phone rotation or Maximized. (Dialog for unlock shown when double-tapped)

\* Even if unlocked, when re-opened, lock will be valid.

Otherwise if shortcut created under Width / Height-BASE or Square size mode, the video called by the shortcut can Auto-Resized by double-Tap when playbacked.

+To Video called from shortcut, can manually Zoom, change speed, clear A-B repeat etc. freely and can create New shortcut from that. (Be careful for back to original shortcut setting when repeated in 'REP' mode)

This feature is Not Video Editing. Only playback setting is saved in shortcut file.  
So changing video file location or renaming video file cause to fail to playback by shortcut.  
Otherwise shortcut file can be located in arbitrary folder, need not in same folder as target video.  
\* shortcut file is simple Text file, so you can edit when changing video file name or location.etc(by selecting 'Open as Text' menu by long-Click shortcut file in this App. For video file full path, you can select long-click video file and select 'Copy Path' in popup menu)

Caution:

When shortcut opened, Start Frame may differ a little from your selected because of Key frame used(in case of Non-Repeat shortcut or Start positio correction feature turned off).

Tips:

+If A or B already selected in Repeat operation, long-press Combo header 'Op' for Reset Repeat.  
In Speed changed, long-press Combo header 'Sped' for Back to Normal Speed as well.

-----  
Playlist for Shortcuts  
-----

When you click a Shortcut, playlist of Shortcuts in current folder is created(background). The Next and Prev Button work according to the playlist.  
(Otherwise when you click 'Video file', playlist including only video files created, not including shortcut)  
Cannot create playlist including both Shortcuts and Video files.

Under PL(Playlist) mode, for shortcut with A-B Repeat, repeat-section playbaced Only Once, and when reached at 'B', Next shortcut played.  
If you would like to playback with repeat A-B section,need to PL button Off.

\* Right after creating shortcut,the shortcut not included in current playlist yet(in case that clicking a shortcut and going to create new shortcut basing that).For adding new shortcut to playlist,click some shortcut file again.