



Kubernetes Volumes



Students, write your response!

Pear Deck Interactive Slide
Do not remove this bar

Table of Contents




- ▶ Volumes
- ▶ Volume Types
- ▶ PersistentVolumes
- ▶ PersistentVolumeClaims
- ▶ The interaction between PVs and PVCs



1

Volumes



Volumes




- on-disk files in a Container are ephemeral.
- All data stored inside a container is deleted if the container crashes.
- When a Container crashes, kubelet will restart it, but the files will be lost which means that it will not have any of the old data.
- To overcome this problem, Kubernetes uses **Volumes**. A Volume is essentially a directory backed by a storage medium. The storage medium, content and access mode are determined by the Volume Type.

Volumes




A **volume** can be thought of as a directory which is accessible to the containers in a pod.



2 Volume Types

Volume Types

- **hostPath:** A hostPath volume mounts a file or directory from the host node's filesystem into your Pod.



Volume Types


- **emptyDir:** An emptyDir volume is first created when a Pod is assigned to a Node and exists as long as that Pod is running on that node.

Some uses for an emptyDir are:

- checkpointing a long computation for recovery from crashes
- as a cache

Volume Types

- **hostPath vs emptyDir**



Volume Types

- **awsElasticBlockStore:** An awsElasticBlockStore volume mounts an Amazon Web Services (AWS) EBS Volume into your Pod.
- **azureDisk:** An azureDisk is used to mount a Microsoft Azure Data Disk into a Pod.
- **gcePersistentDisk:** A gcePersistentDisk volume mounts a Google Compute Engine (GCE) persistent disk (PD) into your Pod.



Volume Types

- **Secret:** A secret volume is used to pass sensitive information, such as passwords, to Pods.
- **configMap:** The configMap resource provides a way to inject configuration data, or shell commands and arguments into a Pod.
- **persistentVolumeClaim:** A persistentVolumeClaim volume is used to mount a PersistentVolume into a Pod.



3

PersistentVolumes

PersistentVolumes

A **PersistentVolume (PV)** is a piece of storage in the cluster that has been provisioned by an administrator or dynamically provisioned using Storage Classes.



PersistentVolumeClaims


PersistentVolumeClaims

A **PersistentVolumeClaim (PVC)** is a request for storage by a user. Users request for PersistentVolume resources based on type, access mode, and size. There are four access modes:

- **ReadWriteOnce** (read-write by a single node)
- **ReadOnlyMany** (read-only by many nodes)
- **ReadWriteMany** (read-write by many nodes).
- **ReadWriteOncePod** (read-write only one pod in the cluster)

Once a suitable **PersistentVolume** is found, it is bound to a **PersistentVolumeClaim**.

PersistentVolumeClaims






5

The interaction between PVs and PVCs

The interaction between PVs and PVCs



The interaction between PVs and PVCs


Static



Dynamic




Static PV Provisioning





Administrator



21



THANKS!

Any questions?

You can find me at:

- ▶ james@clarusway.com



Students, write your response!

Dynamic PV Provisioning

A **StorageClass** provides a way for administrators to describe the "classes" of storage they offer.

