

How to Configure WP Mail SMTP on WordPress

This is a quick walk through on how to setup the WP Mail SMTP on your WordPress site.

1. First, make sure you've installed and activated **WP Mail SMTP** plugin.

2. Then configure the WP Mail SMTP plugin

From Email: **itec464@teeblissenterprises.com** (Do not change this From Email)

From Name: **ITEC 464 WordPress**

Make sure you select **Other SMTP** radio button from the Mailer options.

SMTP Host: **live.smtp.mailtrap.io**

SMTP Port: **587**

SMTP Username: **api**

SMTP Password: **4f25ba2056ab180ae46ac1faae2fb98d**

After that, scroll down and click "Save Settings"

that's it!

*** Check the screenshots below to make sure your settings match exactly ***

How to Configure WP Mail SMTP on WordPress

ITEC 464 WordPress

20

New

Dashboard

Posts

Media

Pages

Comments

Appearance

Plugins

Users

Tools

Settings

WP Mail SMTP

Settings

Email Log

Email Reports

Tools

About Us

Upgrade to Pro

Inquiry Request Example

Collapse menu

WP Mail SMTP

a wpforms product

GeneralEmail LogAlertsAdditional ConnectionsSmart RoutingEmail ControlsMisc

License

Your license key provides access to updates and support.

License Key

You're using WP Mail SMTP Lite - no license needed. Enjoy! 😊

To unlock more features, consider [upgrading to PRO](#).

As a valued WP Mail SMTP Lite user you receive \$50 off, automatically applied at checkout!

Already purchased? Simply enter your license key below to connect with WP Mail SMTP Pro!

Paste license key here

Connect

Primary Connection

Setup Wizard

Launch Setup Wizard

We'll guide you through each step needed to get WP Mail SMTP fully set up on your site.

From Email

itec464@teeblissenterprises.com

The email address that emails are sent from.

How to Configure WP Mail SMTP on WordPress

ITEC 464 WordPress

20

New

Dashboard

Posts

Media

Pages

Comments

Appearance

Plugins

Users

Tools

Settings

WP Mail SMTP

Settings

Email Log

Email Reports

Tools

About Us

Upgrade to Pro

Inquiry Request Example

Collapse menu

From Email

itec464@teeblissenterprises.com

The email address that emails are sent from.

If you're using an email provider (Yahoo, Outlook.com, etc) this should be your email address for that account.

Please note that other plugins can change this, to prevent this use the setting below.

Force From Email

OFF

If checked, the From Email setting above will be used for all emails, ignoring values set by other plugins.

From Name

ITEC 464 WordPress

The name that emails are sent from.

Force From Name

ON

If checked, the From Name setting above will be used for all emails, ignoring values set by other plugins.

Return Path

OFF

Return Path indicates where non-delivery receipts - or bounce messages - are to be sent.

If unchecked, bounce messages may be lost.

Mailer

php

Default (none)

SendLayer

SendLayer

SMTP

SMTP.com

Brevo

Brevo

aws

Amazon SES

Google

Google / Gmail

mailgun

Mailgun

365 / Outlook

365 / Outlook

Postmark

Postmark

SendGrid

SendGrid

SPARKPOST

SparkPost

zoho

Zoho Mail

Other SMTP

Other SMTP

Don't see what you're looking for? [Suggest a Mailer](#)

Other SMTP

The Other SMTP option lets you send emails through an SMTP server instead of using a provider's API. This is easy and convenient, but it's less secure than

How to Configure WP Mail SMTP on WordPress

Dashboard

Posts

Media

Pages

Comments

Appearance

Plugins

Users

Tools

Settings

WP Mail SMTP

Settings

Email Log

Email Reports

Tools

About Us

Upgrade to Pro

Inquiry Request Example

Collapse menu

Other SMTP

The Other SMTP option lets you send emails through an SMTP server instead of using a provider's API. This is easy and convenient, but it's less secure than the other mailers. Please note that your provider may not allow you to send a large number of emails. In that case, please use a different mailer.

To get started, read our [Other SMTP documentation](#).

SMTP Host

live.smtp.mailtrap.io

Encryption

☒ None

☐ SSL

☐ TLS

For most servers TLS is the recommended option. If your SMTP provider offers both SSL and TLS options, we recommend using TLS.

SMTP Port

587

Auto TLS

☒ ON

By default, TLS encryption is automatically used if the server supports it (recommended). In some cases, due to server misconfigurations, this can cause issues and may need to be disabled.

Authentication

☒ ON

SMTP Username

api

SMTP Password

.....

The password is encrypted in the database, but for improved security we recommend using your site's WordPress configuration file to set your password.

[Learn More](#)

Backup Connection

PRO

Don't worry about losing emails. Add an additional connection, then set it as your Backup Connection. Emails that fail to send with the Primary Connection will be sent via the selected Backup Connection. [Upgrade to WP Mail SMTP Pro!](#)

Backup Connection

☒ None

Once you add an [additional connection](#), you can select it here.

Save Settings