

[Windows - Error Codes](#)[Windows - Error Codes](#)[Win32 - Error Codes \(1000 - 1999\)](#)

Win32 - Error Codes (0 - 999)

The following table provides a list of Win32 error codes.

Code	Description	Name
0	The operation completed successfully.	ERROR_SUCCESS
1	Incorrect function.	ERROR_INVALID_FUNCTION
2	The system cannot find the file specified.	ERROR_FILE_NOT_FOUND
3	The system cannot find the path specified.	ERROR_PATH_NOT_FOUND
4	The system cannot open the file.	ERROR_TOO_MANY_OPEN_FILES
5	Access is denied.	ERROR_ACCESS_DENIED
6	The handle is invalid.	ERROR_INVALID_HANDLE
7	The storage control blocks were destroyed.	ERROR_ARENA_TRASHED
8	Not enough storage is available to process this command.	ERROR_NOT_ENOUGH_MEMORY
9	The storage control block address is invalid.	ERROR_INVALID_BLOCK
10	The environment is incorrect.	ERROR_BAD_ENVIRONMENT
11	An attempt was made to load a program with an incorrect format.	ERROR_BAD_FORMAT
12	The access code is invalid.	ERROR_INVALID_ACCESS
13	The data is invalid.	ERROR_INVALID_DATA
14	Not enough storage is available to complete this operation.	ERROR_OUTOFMEMORY
15	The system cannot find the drive specified.	ERROR_INVALID_DRIVE
16	The directory cannot be removed.	ERROR_CURRENT_DIRECTORY
17	The system cannot move the file to a different disk drive.	ERROR_NOT_SAME_DEVICE
18	There are no more files.	ERROR_NO_MORE_FILES
19	The media is write protected.	ERROR_WRITE_PROTECT
20	The system cannot find the device specified.	ERROR_BAD_UNIT
21	The device is not ready.	ERROR_NOT_READY
22	The device does not recognize the command.	ERROR_BAD_COMMAND
23	Data error (cyclic redundancy check).	ERROR_CRC
24	The program issued a command but the command length is incorrect.	ERROR_BAD_LENGTH
25	The drive cannot locate a specific area or track on the disk.	ERROR_SEEK
26	The specified disk or diskette cannot be accessed.	ERROR_NOT_DOS_DISK
27	The drive cannot find the sector requested.	ERROR_SECTOR_NOT_FOUND
28	The printer is out of paper.	ERROR_OUT_OF_PAPER
29	The system cannot write to the specified device.	ERROR_WRITE_FAULT
30	The system cannot read from the specified device.	ERROR_READ_FAULT
31	A device attached to the system is not functioning.	ERROR_GEN_FAILURE
32	The process cannot access the file because it is being used by another process.	ERROR_SHARING_VIOLATION
33	The process cannot access the file because another process has locked a portion of the file.	ERROR_LOCK_VIOLATION

34	The wrong diskette is in the drive. Insert %2 (Volume Serial Number: %3) into drive %1.	ERROR_WRONG_DISK
36	Too many files opened for sharing.	ERROR_SHARING_BUFFER_EXCEEDED
38	Reached the end of the file.	ERROR_HANDLE_EOF
39	The disk is full.	ERROR_HANDLE_DISK_FULL
50	The network request is not supported.	ERROR_NOT_SUPPORTED
51	The remote computer is not available.	ERROR_REM_NOT_LIST
52	A duplicate name exists on the network.	ERROR_DUP_NAME
53	The network path was not found.	ERROR_BAD_NETPATH
54	The network is busy.	ERROR_NETWORK_BUSY
55	The specified network resource or device is no longer available.	ERROR_DEV_NOT_EXIST
56	The network BIOS command limit has been reached.	ERROR_TOO_MANY_CMDS
57	A network adapter hardware error occurred.	ERROR_ADAP_HDW_ERR
58	The specified server cannot perform the requested operation.	ERROR_BAD_NET_RESP
59	An unexpected network error occurred.	ERROR_UNEXP_NET_ERR
60	The remote adapter is not compatible.	ERROR_BAD_REM_ADAP
61	The printer queue is full.	ERROR_PRINTQ_FULL
62	Space to store the file waiting to be printed is not available on the server.	ERROR_NO_SPOOL_SPACE
63	Your file waiting to be printed was deleted.	ERROR_PRINT_CANCELED
64	The specified network name is no longer available.	ERROR_NETNAME_DELETED
65	Network access is denied.	ERROR_NETWORK_ACCESS_DENIED
66	The network resource type is not correct.	ERROR_BAD_DEV_TYPE
67	The network name cannot be found.	ERROR_BAD_NET_NAME
68	The name limit for the local computer network adapter card was exceeded.	ERROR_TOO_MANY_NAMES
69	The network BIOS session limit was exceeded.	ERROR_TOO_MANY_SESS
70	The remote server has been paused or is in the process of being started.	ERROR_SHARING_PAUSED
71	No more connections can be made to this remote computer at this time because there are already as many connections as the computer can accept.	ERROR_REQ_NOT_ACCEP
72	The specified printer or disk device has been paused.	ERROR_REDIR_PAUSED
80	The file exists.	ERROR_FILE_EXISTS
82	The directory or file cannot be created.	ERROR_CANNOT_MAKE
83	Fail on INT 24.	ERROR_FAIL_I24
84	Storage to process this request is not available.	ERROR_OUT_OF_STRUCTURES
85	The local device name is already in use.	ERROR_ALREADY_ASSIGNED
86	The specified network password is not correct.	ERROR_INVALID_PASSWORD
87	The parameter is incorrect.	ERROR_INVALID_PARAMETER
88	A write fault occurred on the network.	ERROR_NET_WRITE_FAULT
89	The system cannot start another process at this time.	ERROR_NO_PROC_SLOTS
100	Cannot create another system semaphore.	ERROR_TOO_MANY_SEMAPHORES
101	The exclusive semaphore is owned by another process.	ERROR_EXCL_SEM_ALREADY_OWNED
102	The semaphore is set and cannot be closed.	ERROR_SEM_IS_SET
103	The semaphore cannot be set again.	ERROR_TOO_MANY_SEM_REQUESTS
104	Cannot request exclusive semaphores at interrupt time.	ERROR_INVALID_AT_INTERRUPT_TIME
105	The previous ownership of this semaphore has ended.	ERROR_SEM_OWNER_DIED
106	Insert the diskette for drive %1.	ERROR_SEM_USER_LIMIT
107	The program stopped because an alternate diskette was not inserted.	ERROR_DISK_CHANGE

108	The disk is in use or locked by another process.	ERROR_DRIVE_LOCKED
109	The pipe has been ended.	ERROR_BROKEN_PIPE
110	The system cannot open the device or file specified.	ERROR_OPEN_FAILED
111	The file name is too long.	ERROR_BUFFER_OVERFLOW
112	There is not enough space on the disk.	ERROR_DISK_FULL
113	No more internal file identifiers available.	ERROR_NO_MORE_SEARCH_HANDLES
114	The target internal file identifier is incorrect.	ERROR_INVALID_TARGET_HANDLE
117	The IOCTL call made by the application program is not correct.	ERROR_INVALID_CATEGORY
118	The verify-on-write switch parameter value is not correct.	ERROR_INVALID_VERIFY_SWITCH
119	The system does not support the command requested.	ERROR_BAD_DRIVER_LEVEL
120	This function is not supported on this system.	ERROR_CALL_NOT_IMPLEMENTED
121	The semaphore timeout period has expired.	ERROR_SEM_TIMEOUT
122	The data area passed to a system call is too small.	ERROR_INSUFFICIENT_BUFFER
123	The filename, directory name, or volume label syntax is incorrect.	ERROR_INVALID_NAME
124	The system call level is not correct.	ERROR_INVALID_LEVEL
125	The disk has no volume label.	ERROR_NO_VOLUME_LABEL
126	The specified module could not be found.	ERROR_MOD_NOT_FOUND
127	The specified procedure could not be found.	ERROR_PROC_NOT_FOUND
128	There are no child processes to wait for.	ERROR_WAIT_NO_CHILDREN
129	The %1 application cannot be run in Win32 mode.	ERROR_CHILD_NOT_COMPLETE
130	Attempt to use a file handle to an open disk partition for an operation other than raw disk I/O.	ERROR_DIRECT_ACCESS_HANDLE
131	An attempt was made to move the file pointer before the beginning of the file.	ERROR_NEGATIVE_SEEK
132	The file pointer cannot be set on the specified device or file.	ERROR_SEEK_ON_DEVICE
133	A JOIN or SUBST command cannot be used for a drive that contains previously joined drives.	ERROR_IS_JOIN_TARGET
134	An attempt was made to use a JOIN or SUBST command on a drive that has already been joined.	ERROR_IS_JOINED
135	An attempt was made to use a JOIN or SUBST command on a drive that has already been substituted.	ERROR_IS_SUBSTED
136	The system tried to delete the JOIN of a drive that is not joined.	ERROR_NOT_JOINED
137	The system tried to delete the substitution of a drive that is not substituted.	ERROR_NOT_SUBSTED
138	The system tried to join a drive to a directory on a joined drive.	ERROR_JOIN_TO_JOIN
139	The system tried to substitute a drive to a directory on a substituted drive.	ERROR_SUBST_TO_SUBST
140	The system tried to join a drive to a directory on a substituted drive.	ERROR_JOIN_TO_SUBST
141	The system tried to SUBST a drive to a directory on a joined drive.	ERROR_SUBST_TO_JOIN
142	The system cannot perform a JOIN or SUBST at this time.	ERROR_BUSY_DRIVE
143	The system cannot join or substitute a drive to or for a directory on the same drive.	ERROR_SAME_DRIVE
144	The directory is not a subdirectory of the root directory.	ERROR_DIR_NOT_ROOT
145	The directory is not empty.	ERROR_DIR_NOT_EMPTY
146	The path specified is being used in a substitute.	ERROR_IS_SUBST_PATH
147	Not enough resources are available to process this command.	ERROR_IS_JOIN_PATH
148	The path specified cannot be used at this time.	ERROR_PATH_BUSY
149	An attempt was made to join or substitute a drive for which a directory on the drive is the target of a previous substitute.	ERROR_IS_SUBST_TARGET

150	System trace information was not specified in your CONFIG.SYS file, or tracing is disallowed.	ERROR_SYSTEM_TRACE
151	The number of specified semaphore events for DosMuxSemWait is not correct.	ERROR_INVALID_EVENT_COUNT
152	DosMuxSemWait did not execute; too many semaphores are already set.	ERROR_TOO_MANY_MUXWAITERS
153	The DosMuxSemWait list is not correct.	ERROR_INVALID_LIST_FORMAT
154	The volume label you entered exceeds the label character limit of the target file system.	ERROR_LABEL_TOO_LONG
155	Cannot create another thread.	ERROR_TOO_MANY_TCBS
156	The recipient process has refused the signal.	ERROR_SIGNAL_REFUSED
157	The segment is already discarded and cannot be locked.	ERROR_DISCARDED
158	The segment is already unlocked.	ERROR_NOT_LOCKED
159	The address for the thread ID is not correct.	ERROR_BAD_THREADID_ADDR
160	The argument string passed to DosExecPgm is not correct.	ERROR_BAD_ARGUMENTS
161	The specified path is invalid.	ERROR_BAD_PATHNAME
162	A signal is already pending.	ERROR_SIGNAL_PENDING
164	No more threads can be created in the system.	ERROR_MAX_THRDS_REACHED
167	Unable to lock a region of a file.	ERROR_LOCK_FAILED
170	The requested resource is in use.	ERROR_BUSY
173	A lock request was not outstanding for the supplied cancel region.	ERROR_CANCEL_VIOLATION
174	The file system does not support atomic changes to the lock type.	ERROR_ATOMIC_LOCKS_NOT_SUPPORTED
180	The system detected a segment number that was not correct.	ERROR_INVALID_SEGMENT_NUMBER
182	The operating system cannot run %1.	ERROR_INVALID_ORDINAL
183	Cannot create a file when that file already exists.	ERROR_ALREADY_EXISTS
186	The flag passed is not correct.	ERROR_INVALID_FLAG_NUMBER
187	The specified system semaphore name was not found.	ERROR_SEM_NOT_FOUND
188	The operating system cannot run %1.	ERROR_INVALID_STARTING_CODESEG
189	The operating system cannot run %1.	ERROR_INVALID_STACKSEG
190	The operating system cannot run %1.	ERROR_INVALID_MODULETYPE
191	Cannot run %1 in Win32 mode.	ERROR_INVALID_EXE_SIGNATURE
192	The operating system cannot run %1.	ERROR_EXE_MARKED_INVALID
193	%1 is not a valid Win32 application.	ERROR_BAD_EXE_FORMAT
194	The operating system cannot run %1.	ERROR_ITERATED_DATA_EXCEEDS_64k
195	The operating system cannot run %1.	ERROR_INVALID_MINALLOCSIZE
196	The operating system cannot run this application program.	ERROR_DYNLINK_FROM_INVALID_RING
197	The operating system is not presently configured to run this application.	ERROR_IOPL_NOT_ENABLED
198	The operating system cannot run %1.	ERROR_INVALID_SEGDPL
199	The operating system cannot run this application program.	ERROR_AUTODATASEG_EXCEEDS_64k
200	The code segment cannot be greater than or equal to 64K.	ERROR_RING2SEG_MUST_BE_MOVABLE
201	The operating system cannot run %1.	ERROR_RELOC_CHAIN_XEEDS_SEGLIM
202	The operating system cannot run %1.	ERROR_INFLOOP_IN_RELOC_CHAIN
203	The system could not find the environment option that was entered.	ERROR_ENVVAR_NOT_FOUND
205	No process in the command subtree has a signal handler.	ERROR_NO_SIGNAL_SENT
206	The filename or extension is too long.	ERROR_FILENAME_EXCED_RANGE
207	The ring 2 stack is in use.	ERROR_RING2_STACK_IN_USE
208	The global filename characters, * or ?, are entered incorrectly or too many global filename characters are specified.	ERROR_META_EXPANSION_TOO_LONG

209	The signal being posted is not correct.	ERROR_INVALID_SIGNAL_NUMBER
210	The signal handler cannot be set.	ERROR_THREAD_1_INACTIVE
212	The segment is locked and cannot be reallocated.	ERROR_LOCKED
214	Too many dynamic-link modules are attached to this program or dynamic-link module.	ERROR_TOO_MANY_MODULES
215	Cannot nest calls to LoadModule.	ERROR_NESTING_NOT_ALLOWED
216	The image file %1 is valid, but is for a machine type other than the current machine.	ERROR_EXE_MACHINE_TYPE_MISMATCH
230	The pipe state is invalid.	ERROR_BAD_PIPE
231	All pipe instances are busy.	ERROR_PIPE_BUSY
232	The pipe is being closed.	ERROR_NO_DATA
233	No process is on the other end of the pipe.	ERROR_PIPE_NOT_CONNECTED
234	More data is available.	ERROR_MORE_DATA
240	The session was canceled.	ERROR_VC_DISCONNECTED
254	The specified extended attribute name was invalid.	ERROR_INVALID_EA_NAME
255	The extended attributes are inconsistent.	ERROR_EA_LIST_INCONSISTENT
258	The wait operation timed out.	WAIT_TIMEOUT
259	No more data is available.	ERROR_NO_MORE_ITEMS
266	The copy functions cannot be used.	ERROR_CANNOT_COPY
267	The directory name is invalid.	ERROR_DIRECTORY
275	The extended attributes did not fit in the buffer.	ERROR_EAS_DIDNT_FIT
276	The extended attribute file on the mounted file system is corrupt.	ERROR_EA_FILE_CORRUPT
277	The extended attribute table file is full.	ERROR_EA_TABLE_FULL
278	The specified extended attribute handle is invalid.	ERROR_INVALID_EA_HANDLE
282	The mounted file system does not support extended attributes.	ERROR_EAS_NOT_SUPPORTED
288	Attempt to release mutex not owned by caller.	ERROR_NOT_OWNER
298	Too many posts were made to a semaphore.	ERROR_TOO_MANY_POSTS
299	Only part of a ReadProcessMemory or WriteProcessMemory request was completed.	ERROR_PARTIAL_COPY
300	The oplock request is denied.	ERROR_OPLOCK_NOT_GRANTED
301	An invalid oplock acknowledgment was received by the system.	ERROR_INVALID_OPLOCK_PROTOCOL
317	The system cannot find message text for message number 0x%1 in the message file for %2.	ERROR_MR_MID_NOT_FOUND
487	Attempt to access invalid address.	ERROR_INVALID_ADDRESS
534	Arithmetic result exceeded 32 bits.	ERROR_ARITHMETIC_OVERFLOW
535	There is a process on other end of the pipe.	ERROR_PIPE_CONNECTED
536	Waiting for a process to open the other end of the pipe.	ERROR_PIPE_LISTENING
994	Access to the extended attribute was denied.	ERROR_EA_ACCESS_DENIED
995	The I/O operation has been aborted because of either a thread exit or an application request.	ERROR_OPERATION_ABORTED
996	Overlapped I/O event is not in a signaled state.	ERROR_IO_INCOMPLETE
997	Overlapped I/O operation is in progress.	ERROR_IO_PENDING
998	Invalid access to memory location.	ERROR_NOACCESS
999	Error performing inpage operation.	ERROR_SWAPERROR