

Table 22. Define PFD Specifications display fields (continued)

Field Name	Description
Measurement method	<p>Specifies the measurement method to be used for the offset.</p> <p>Possible values are:</p> <ol style="list-style-type: none"> 1 Row/Column is used as the measurement method. 2 Either inch or centimeter is used as the measurement method depending on the value specified for the unit of measure. <p>Note: To change both the measurement method and its following fields, change the value for the measurement method and press the Enter key before you change the following fields. The following fields specify the offset of the page layout.</p>
Across	<p>Specifies the value of the horizontal distance from the left edge of the logical page to the origin of the element to be created. The valid values are:</p> <ul style="list-style-type: none"> • 0 to 999 (columns) • 0 to 22.75 (inches) • 0 to 57.79 (centimeters)
Down	<p>Specifies the value of the vertical distance from the top edge of the logical page to the origin of the element to be created. The valid values are:</p> <ul style="list-style-type: none"> • 0 to 999 (rows) • 0 to 22.75 (inches) • 0 to 57.79 (centimeters)
Grid	<p>The grid is the combination of lines at regular intervals, and is defined by the measurement method, the across (horizontal interval), and the down (vertical interval).</p>
Measurement method	<p>Specifies the measurement method being used for the grid.</p> <p>Possible values are:</p> <ol style="list-style-type: none"> 1 Row/Column is used as the measurement method. 2 Either inch or centimeter is used as the measurement method depending on the value specified for the unit of measure. <p>Note: To change both the measurement method and its following fields, change the value for the measurement method and press the Enter key before changing the following fields.</p>
Across	<p>You can specify to print horizontal and vertical lines with the printout to help your designing work. The following fields specify the horizontal and vertical distances between grid lines.</p> <p>Specifies the value of the horizontal distance from the left edge of the logical page to the origin of the element to be created. The valid values are:</p> <ul style="list-style-type: none"> • 1 - 999 (columns) • 0.10 - 22.75 (inches) • 0.10 - 57.79 (centimeters)
Down	<p>Specifies the value of the vertical distance from the top edge of the logical page to the origin of the element to be created. The valid values are:</p> <ul style="list-style-type: none"> • 1 - 999 (rows) • 0.10 - 22.75 (inches) • 0.10 - 57.79 (centimeters)