



如何修改Jupyter Notebook的启动文件夹

如果你的电脑已经将Python及Anaconda的加到了环境变量里面，那么可以在Windows的文件浏览器的地址栏直接输入 `jupyter notebook`。




此外可以通过如下说明修改默认启动文件夹：

1. 首先进入cmd，如果Python环境变量已经设置成功可以直接在系统打开cmd。如果没有设置环境变量，可以从开始菜单anaconda下选择进入，如下图所示：




2. 在cmd下，输入 `jupyter notebook --generate-config`



```
(base) C:\Windows\System32>jupyter notebook --generate-config
Writing default config to: C:\Users\...\.jupyter\jupyter_notebook_config.py
(base) C:\Windows\System32>
```

请注意涂黑部分应该是你自己电脑的用户名

3. 打开对应路径下的对应文件（应该是C盘用户（user）-你的用户名 这个文件夹下 jupyter_notebook_config.py），搜索“c.NotebookApp.notebook_dir”，版本不同也可能是“c.ServerApp.root_dir”，请注意画线部分上面的注释应该是“The directory to use for notebooks and kernels.”



```
957
958 ## Preferred starting directory to use for notebooks and kernels.
959 # ServerApp.preferred_dir is deprecated in jupyter-server 2.0. Use
960 # FileContentsManager.preferred_dir instead
961 # Default: ''
962 # c.ServerApp.preferred_dir = ''
963
964 ## DISABLED: use %pylab or %matplotlib in the notebook to enable matplotlib.
965 # Default: 'disabled'
966 # c.ServerApp.pylab = 'disabled'
967
968 ## If True, display controls to shut down the Jupyter server, such as menu items
969 # or buttons.
970 # Default: True
971 # c.ServerApp.quit_button = True
972
973 ## DEPRECATED. Use ZMQChannelsWebsocketConnection.rate_limit_window
974 # Default: 0.0
975 # c.ServerApp.rate_limit_window = 0.0
976
977 ## Reraise exceptions encountered loading server extensions?
978 # Default: False
979 # c.ServerApp.reraise_server_extension_failures = False
980
981 ## The directory to use for notebooks and kernels.
982 # Default: ''
983 # c.ServerApp.root_dir = ''
984
```

4. 取消该行注释（删掉最前方的#），在等号后面的引号中输入新的文件夹路径

```
981  ## The directory to use for notebooks and kernels.  
982  # Default: ''  
983  c.ServerApp.root_dir = r'c:\newfolder'  
984
```

5. 关闭所有应用，重启电脑路径应该就修改好了