



## [BannerSlider GraphQL User Guide](#)

# How to install the extension

## 1. Install via composer (recommend)

- Enable maintenance mode **php bin/magento maintenance:enable**
- Run the command **composer require banner-slider-graphql**
- Run the command **php bin/magento module:enable MagelNIC\_Core MagelNIC\_BannerSliderGraphql**
- Run the command **php bin/magento setup:upgrade** to install the extension
- Run the command **php bin/magento cache:clean** to clean the cache
- Disable maintenance mode **php bin/magento maintenance:disable**
- Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.

## 2. Upload via ZIP/Archive

- Back up your store's database and web directory
  - Download the extension zip file and extract the zip file
  - Transfer the **MagelNIC** folder to the Magento 2 **app/code/** directory on the server
  - Enable maintenance mode **php bin/magento maintenance:enable**
  - Run the command **php bin/magento module:enable MagelNIC\_Core MagelNIC\_BannerSliderGraphql**
  - Run the command **php bin/magento setup:upgrade** to install the extension
  - Run the command **php bin/magento cache:clean** to clean the cache
  - Disable maintenance mode **php bin/magento maintenance:disable**
  - Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.
- 

## Store Configuration

- Please include the following query in the body section to fetch the module store configuration values.

**End Point :** {{baseurl}}/graphql  
**Method:** POST

**Request:**



```

{
  storeConfig {
    banner_slider_general_enable
    banner_slider_general_enable_at_home
    banner_slider_general_home_slider
    banner_slider_color_option
    banner_slider_navbar
    banner_slider_arrow
    banner_slider_autoplay
    banner_slider_dots
    banner_slider_infinite_looping
    banner_slider_autoplay_speed
    banner_slider_breakpoints
    banner_slider_speed
  }
}

```

#### Response :

```

{
  "data": {
    "storeConfig": {
      "banner_slider_general_enable": "1",
      "banner_slider_general_enable_at_home": "1",
      "banner_slider_general_home_slider": null,
      "banner_slider_color_option": "#ffffff",
      "banner_slider_navbar": "1",
      "banner_slider_arrow": "1",
      "banner_slider_autoplay": "1",
      "banner_slider_dots": "1",
      "banner_slider_infinite_looping": "1",
      "banner_slider_autoplay_speed": "2000",
      "banner_slider_breakpoints":
        "{ \"item1\": { \"breakpoint\": \"1024\", \"slides_to_show\": \"1\", \"slides_to_scroll\": \"1\", \"dots\": \"1\" }, \"item2\": { \"breakpoint\": \"992\", \"slides_to_show\": \"1\", \"slides_to_scroll\": \"1\", \"dots\": \"1\" }, \"item3\": { \"breakpoint\": \"480\", \"slides_to_show\": \"1\", \"slides_to_scroll\": \"1\", \"dots\": \"1\" } }",
      "banner_slider_speed": "400"
    }
  }
}

```

```
}
```

## Store Configuration

### Banner Slider List

- To implement store-specific banner slider filtering, it is essential to configure the Header with the Key: "Store" and Value: "Default" (using your Store Code). This setup ensures effective segregation of banner slider based on individual store contexts.

#### Request:

```
query{
  Slider(filter: {slider_id:{eq:"YourSliderId"}},pageSize: 5, currentPage: 1) {
    items {
      slider_id
      title
      Banner{
        items{
          banner_id
          slider_id
          name
          link
          media
          media_alt
          caption
        }
      }
    }
    total_count
  }
}
```

## Response

```
{
  "data": {
    "Slider": {
      "items": [
        {
          "slider_id": "1",
          "title": "Home Page",
          "Banner": {
            "items": [
              {
                "banner_id": 1,
                "slider_id": "1",
                "name": "Banner1",
                "link": "https://www.lipsum.com/",
                "media":
"https://test.mageinic.com/media/MageINIC/bannerslider/banner1.jpg",
                "media_alt": "Banner1",
                "caption": "<div data-content-type=\"html\" data-appearance=\"default\"
data-element=\"main\">&lt;p&gt;Lorem Ipsum is simply dummy text of the printing and
typesetting industry. Lorem Ipsum has been the industry's standard dummy text ever since the
1500s, when an unknown printer took a galley of type and scrambled it to make a type
specimen book. It has survived not only five centuries, but also the leap into electronic
typesetting, remaining essentially unchanged. It was popularised in the 1960s with the release
of Letraset sheets containing Lorem Ipsum passages, and more recently with desktop
publishing software like Aldus PageMaker including versions of Lorem Ipsum.&lt;/p&gt;</div>"
              },
              {
                "banner_id": 2,
                "slider_id": "1",
                "name": "Banner2",
                "link": "https://www.lipsum.com/",
```

```
        "media":
"https://test.mageinic.com/media/MageINIC/bannerslider/sample-video.mp4",
        "media_alt": "video",
        "caption": ""
    }
]
}
},
],
"total_count": null
}
}
}
```

## Note

- In the Yes/no dropdown, the value of "Yes" corresponds to "1," while the value of "No" corresponds to "0."