

Michael Teitelbaum - 500747561

Mark Volfson - 500740834

Elena Zubko - 500768733

Dr. Jelena Misic

CPS 706

April 10, 2019

CPS 706 Project Documentation

User Documentation

Getting Started

In order for the application to work, you have to first initialize a few DHT (Distributed Hash Table) servers that will store the IP addresses for each of the files in the network. Each of the clients need to initialize them serves using the code provided in the network that will allow them to get the IP of the desired files, and download/upload files as desired by the network.

Here are the instructions needed to begin the application:

Initializing DHT Servers

To start the peer-to-peer network you first have to initialize 1 or more DHT servers on the network that will store the IP addresses of the clients.

In order to do so you will need to locate the DHT source files in the directories as seen above and run the following lines on the command line of your machine. Please make sure that your command line is pointed to the DHT Server directory.

```
>> java -jar "DHT Server.jar"
```

Executing the above line will start the DHT server. The first line that appears will be the IP address of your local machine. The second line will ask you to enter the ID number for the given DHT server. The numbering for the servers begins with 0. Once the ID is entered, the application will ask you to enter the IP address of the successor DHT server. In the case of multiple DHT servers, please make sure you assign the ID's in sequence and specify the correct IP for the next DHT server. If you are running only one DHT server then enter your personal IP address in the successor IP field.

Once all of the above information is entered, the output should look like this:

```
>> [Machine Local IP]
>> Enter ID: [ID number]
>> Enter successor server IP: [Successor IP Address]
UDP server has been successfully initialized!
TCP server has been successfully initialized!
```

```
All systems working properly!
```

Next step is for each of the client(s) (user(s) for the P2P network) to initialize themselves in the network.

Initializing Each User


There can be any amount of users in the network. To begin using this application, each user has to initialize themselves on the network. This is done by running a JAVA program on each clients local machine.

Each client needs to follow the below steps to start exchanging files

First, run the "Client Server.jar" file either by double-clicking the file or by running the following command in powershell:

```
>> java -jar "Client Server.jar"
```

When first started, you will be presented with the following window:



The screenshot shows a window titled "P2P Client Application". It contains four input fields with corresponding labels and buttons:

- Directory To Share:** A text input field with a "Select" button to its right.
- Save To Directory:** A text input field with a "Select" button to its right.
- DHT Server ID:** A text input field.
- DHT Server IP:** A text input field.

At the bottom center of the form is an "Accept" button.

Here you will select the directory of both the folder of photos you wish to share, and the folder to save downloaded photos to. You will also enter the ID and the IP of the initial known DHT Server.

After filling out the information and pressing accept, the client and server of the P2P member will be started and you will be presented with the following window:

The screenshot shows a web application window titled "P2P Client Application". The main heading is "The Cloud Network". Below the heading, there is a prompt: "Enter the name of the content you wish to download below: Extension Included". This is followed by a label "Content Name:" and a text input field. To the right of the input field is a "Download" button. Below the input field, there is a "Status:" label. Underneath the status label are two buttons: "Open Shared Files Directory" and "Open Saved Files Directory".

Here, you can open the directories that you have chosen and put in the name of the file(including extension) you wish to download. If downloaded successfully, you will get a "File Successfully Downloaded" message or an error message if there were any problems.

System Documentation

The content names with the corresponding member IP are held in the DHT servers in a hash table. This made the process of retrieving the IP corresponding to the content more efficient.

UDP (Member to DHT server):

- Initialize
 - Send request to DHT server
 - Receive list of all DHT servers
- Inform and update
 - Send content with member IP to DHT corresponding with the content name hash value
- Query for content
 - Send request to DHT server corresponding to content name hash value
 - Receive member IP with the content
- Exit
 - Send request to DHT server to remove entries with the member IP from all DHT servers

TCP (DHT server to DHT server):

- Client initializes
 - Each DHT server appends its ID and IP to the final string
 - When each DHT server's IP is present in the final string, send it to the client using UDP
- Client exits
 - Client sends to server its IP address
 - Iterates through all DHT servers to remove all values corresponding to that IP from the hash table

TCP (Member to Member):

- Send request to other member for content
- Returns either the requested content or an error

Program Architecture

