


# How to Create an Endpoint Detection and Response Profile in Microsoft Endpoint Manager

1 Navigate to [endpoint.microsoft.com](https://endpoint.microsoft.com)

2 Click "Create Policy"



3

Platform: Windows  
Profile: Endpoint detection and response

**Create a profile**

Platform  
Windows 10, Windows 11, and Windows Server

Profile  
Select a profile  
Endpoint detection and response

Assigned	Platform
Yes	Windows 10 and later

4

Create a name and description for your profile.

Home / Endpoint security / Endpoint detection and response

## Create profile

Endpoint detection and response

1 Basics 2 Configuration settings 3 Scope tags 4 Assignments 5 Review + create

Name \* EDR-Baseline-Profile ✓

Description This EDR profile applies to all Business Premium users

Platform Windows 10 and later

## 5 Click "Not configured"

Home > Endpoint security | Endpoint detection and response >

### Create profile

Endpoint detection and response

1 Basics 2 Configuration settings 3 Scope tags 4 Assignments 5 Review + create

Microsoft Defender for Endpoint

Microsoft Defender for Endpoint client configuration package type ① Not configured

Sample Sharing ① Not configured

Telemetry Reporting Frequency ① Not configured

## 6 Click here.

Create profile

Endpoint detection and response

1 Basics 2 Configuration settings 3 Scope tags 4 Assignments 5 Review + create

Microsoft Defender for Endpoint

Microsoft Defender for Endpoint client configuration package type ①

Sample Sharing ①

Telemetry Reporting Frequency ①

Not configured

Auto from connector

Onboard

Offboard

Not configured

Not configured

## 7 Click "Onboard"

Home > Endpoint security | Endpoint detection and response >

### Create profile

Endpoint detection and response

1 Basics 2 Configuration settings 3 Scope tags 4 Assignments 5 Review + create

Microsoft Defender for Endpoint

Microsoft Defender for Endpoint client configuration package type ⓘ

Onboarding (Device) \* ⓘ

Sample Sharing ⓘ

Telemetry Reporting Frequency ⓘ

Onboard

Not configured

Not configured

## 8 Click "Auto from connector"

Home > Endpoint security | Endpoint detection and response >

### Create profile

Endpoint detection and response

1 Basics 2 Configuration settings 3 Scope tags 4 Assignments 5 Review + create

Microsoft Defender for Endpoint

Microsoft Defender for Endpoint client configuration package type ⓘ

Onboarding (Device) \* ⓘ

Sample Sharing ⓘ

Telemetry Reporting Frequency ⓘ

Onboard

Auto from connector

Onboard

Offboard

Not configured

Not configured

9

Configuration Package Type: Auto  
Sample Sharing: All  
Telemetry Reporting Frequency: Normal

Home / Endpoint security / Endpoint detection and response /

## Create profile

Endpoint detection and response

1 Basics 2 Configuration settings 3 Scope tags 4 Assignments 5 Review + create

Microsoft Defender for Endpoint

Microsoft Defender for Endpoint client configuration package type ①

Auto from connector

Sample Sharing ①

All

Telemetry Reporting Frequency ①

Normal

10

Target the desired groups and click "Create"

Scope tags

Default

Assignments

Included groups

Group	Group Members ①	Filter	Filter
M365.BusinessPremium.Enabled	0 devices, 3 users	None	None

Excluded groups

Group	Group Members ①
No results.	

Previous Create