

## seid tx gov submit-proposal set-contract-admin

Submit a new admin for a contract proposal

Usage: `seid tx gov submit-proposal set-contract-admin [contract_addr_bech32] [new_admin_addr_bech32] [flags]`

Flags: `-a`, `--account-number` uint The account number of the signing account (offline mode only) `-b`, `--broadcast-mode` string Transaction broadcasting mode (`sync|async|block`) (default `"sync"`) `--deposit` string Deposit of proposal `--description` string Description of proposal `--dry-run` ignore the `--gas` flag and perform a simulation of a transaction, but don't broadcast it (when enabled, the local Keybase is not accessible) `--fee-account` string Fee account pays fees for the transaction instead of deducting from the signer `--fees` string Fees to pay along with transaction; eg: `10uatom` `--from` string Name or address of private key with which to sign `--gas` string gas limit to set per-transaction; set to `"auto"` to calculate sufficient gas automatically (default `200000`) `--gas-adjustment` float adjustment factor to be multiplied against the estimate returned by the tx simulation; if the gas limit is set manually this flag is ignored (default `1`) `--gas-prices` string Gas prices in decimal format to determine the transaction fee (e.g. `0.1uatom`) `--generate-only` Build an unsigned transaction and write it to STDOUT (when enabled, the local Keybase only accessed when providing a key name) `-h`, `--help` help for `set-contract-admin` `--keyring-backend` string Select keyring's backend (`os|file|kwallet|pass|test|memory`) (default `"os"`) `--keyring-dir` string The client Keyring directory; if omitted, the default 'home' directory will be used `--ledger` Use a connected Ledger device `--node` string : to tendermint rpc interface for this chain (default `"tcp://localhost:26657"`) `--note` string Note to add a description to the transaction (previously `--memo`) `--offline` Offline mode (does not allow any online functionality) `-o`, `--output` string Output format (`text|json`) (default `"json"`) `--proposal` string Proposal file path (if this path is given, other proposal flags are ignored) `-s`, `--sequence` uint The sequence number of the signing account (offline mode only) `--sign-mode` string Choose sign mode (`direct|amino-json`), this is an advanced feature `--timeout-height` uint Set a block timeout height to prevent the tx from being committed past a certain height `--title` string Title of proposal `--type` string Permission of proposal, types: `store-code/instantiate/migrate/update-admin/clear-admin/text/parameter_change/software_upgrade` `-y`, `--yes` Skip tx broadcasting prompt confirmation

Global Flags: `--chain-id` string The network chain ID `--home` string directory for config and data (default `"~/sei"`) `--log_format` string The logging format (`json|plain`) `--log_level` string The logging level (`trace|debug|info|warn|error|fatal|panic`) `--trace` print out full stack trace on errors Last updated on July 1, 2024 [pin-codes](#) [software-upgrade](#)