

seid tx evm deploy

Deploy an EVM contract for binary at specified path

Usage: `seid tx evm deploy [path to binary] --from=--gas-fee-cap= --gas-limit= --evm-rpc= [flags]`

Flags: `-a, --account-number uint` The account number of the signing account (offline mode only) `-b, --broadcast-mode string` Transaction broadcasting mode (sync|async|block) (default "sync") `--dry-run` ignore the `--gas` flag and perform a simulation of a transaction, but don't broadcast it (when enabled, the local Keybase is not accessible) `--evm-rpc string` RPC endpoint to send request to (default "http://0.0.0.0:8545") `--fee-account string` Fee account pays fees for the transaction instead of deducting from the signer `--fees string` Fees to pay along with transaction; eg: 10uatom `--from string` Name or address of private key with which to sign `--gas string` gas limit to set per-transaction; set to "auto" to calculate sufficient gas automatically (default 200000) `--gas-adjustment float` adjustment factor to be multiplied against the estimate returned by the tx simulation; if the gas limit is set manually this flag is ignored (default 1) `--gas-fee-cap uint` Gas fee cap for the transaction (default 1000000000000) `--gas-limit uint` Gas limit for the transaction (default 5000000) `--gas-prices string` Gas prices in decimal format to determine the transaction fee (e.g. 0.1uatom) `--generate-only` Build an unsigned transaction and write it to STDOUT (when enabled, the local Keybase only accessed when providing a key name) `-h, --help` help for deploy `--keyring-backend string` Select keyring's backend (os|file|kwallet|pass|test|memory) (default "os") `--keyring-dir string` The client Keyring directory; if omitted, the default 'home' directory will be used `--ledger` Use a connected Ledger device `--node string` : to tendermint rpc interface for this chain (default "tcp://localhost:26657") `--nonce int` Nonce override for the transaction. Negative value means no override (default -1) `--note string` Note to add a description to the transaction (previously `--memo`) `--offline` Offline mode (does not allow any online functionality) `-o, --output string` Output format (text|json) (default "json") `-s, --sequence uint` The sequence number of the signing account (offline mode only) `--sign-mode string` Choose sign mode (direct|amino-json), this is an advanced feature `--timeout-height uint` Set a block timeout height to prevent the tx from being committed past a certain height `-y, --yes` Skip tx broadcasting prompt confirmation

Global Flags: `--chain-id string` The network chain ID `--home string` directory for config and data (default "~/.sei") `--log_format string` The logging format (json|plain) `--log_level string` The logging level (trace|debug|info|warn|error|fatal|panic) `--trace` print out full stack trace on errors Last updated on July 1, 2024 [deploy-wsei erc20-send](#)