

seid tx gov submit-proposal update-instantiate-config

Submit an update instantiate config proposal for multiple code ids.

Example: `tx gov submit-proposal update-instantiate-config 1,nobody 2,everybody 3,sei1l2rsakp388kuv9k8qzq6lrm9taddae7fpx59wm`

Usage: `seid tx gov submit-proposal update-instantiate-config [code-id,permission]... [flags]`

Flags: `-a, --account-number uint` The account number of the signing account (offline mode only) `-b, --broadcast-mode string` Transaction broadcasting mode (sync|async|block) (default "sync") `--deposit string` Deposit of proposal `--description string` Description of proposal `--dry-run` ignore the `--gas` flag and perform a simulation of a transaction, but don't broadcast it (when enabled, the local Keybase is not accessible) `--fee-account string` Fee account pays fees for the transaction instead of deducting from the signer `--fees string` Fees to pay along with transaction; eg: 10uatom `--from string` Name or address of private key with which to sign `--gas string` gas limit to set per-transaction; set to "auto" to calculate sufficient gas automatically (default 200000) `--gas-adjustment float` adjustment factor to be multiplied against the estimate returned by the tx simulation; if the gas limit is set manually this flag is ignored (default 1) `--gas-prices string` Gas prices in decimal format to determine the transaction fee (e.g. 0.1uatom) `--generate-only` Build an unsigned transaction and write it to STDOUT (when enabled, the local Keybase only accessed when providing a key name) `-h, --help` help for update-instantiate-config `--keyring-backend string` Select keyring's backend (os|file|kwallet|pass|test|memory) (default "os") `--keyring-dir string` The client Keyring directory; if omitted, the default 'home' directory will be used `--ledger` Use a connected Ledger device `--node string` : to tendermint rpc interface for this chain (default "tcp://localhost:26657") `--note string` Note to add a description to the transaction (previously `--memo`) `--offline` Offline mode (does not allow any online functionality) `-o, --output string` Output format (text|json) (default "json") `--proposal string` Proposal file path (if this path is given, other proposal flags are ignored) `-s, --sequence uint` The sequence number of the signing account (offline mode only) `--sign-mode string` Choose sign mode (direct|amino-json), this is an advanced feature `--timeout-height uint` Set a block timeout height to prevent the tx from being committed past a certain height `--title string` Title of proposal `--type string` Permission of proposal, types: store-code/instantiate/migrate/update-admin/clear-admin/text/parameter_change/software_upgrade `-y, --yes` Skip tx broadcasting prompt confirmation

Global Flags: `--chain-id string` The network chain ID `--home string` directory for config and data (default "~/.sei") `--log_format string` The logging format (json|plain) `--log_level string` The logging level (trace|debug|info|warn|error|fatal|panic) `--trace` print out full stack trace on errors Last updated on July 1, 2024 [update-client](#) [update-minter](#)