

## seid tx gov vote

Submit a vote for an active proposal. You can find the proposal-id by running "query gov proposals".

Example: tx gov vote 1 yes --from mykey

Usage: seid tx gov vote [proposal-id] [option] [flags]

Flags: -a, --account-number uint The account number of the signing account (offline mode only) -b, --broadcast-mode string Transaction broadcasting mode (sync|async|block) (default "sync") --dry-run ignore the --gas flag and perform a simulation of a transaction, but don't broadcast it (when enabled, the local Keybase is not accessible) --fee-account string Fee account pays fees for the transaction instead of deducting from the signer --fees string Fees to pay along with transaction; eg: 10uatom --from string Name or address of private key with which to sign --gas string gas limit to set per-transaction; set to "auto" to calculate sufficient gas automatically (default 200000) --gas-adjustment float adjustment factor to be multiplied against the estimate returned by the tx simulation; if the gas limit is set manually this flag is ignored (default 1) --gas-prices string Gas prices in decimal format to determine the transaction fee (e.g. 0.1uatom) --generate-only Build an unsigned transaction and write it to STDOUT (when enabled, the local Keybase only accessed when providing a key name) -h, --help help for vote --keyring-backend string Select keyring's backend (os|file|kwallet|pass|test|memory) (default "os") --keyring-dir string The client Keyring directory; if omitted, the default 'home' directory will be used --ledger Use a connected Ledger device --node string : to tendermint rpc interface for this chain (default "tcp://localhost:26657") --note string Note to add a description to the transaction (previously --memo) --offline Offline mode (does not allow any online functionality) -o, --output string Output format (text|json) (default "json") -s, --sequence uint The sequence number of the signing account (offline mode only) --sign-mode string Choose sign mode (direct|amino-json), this is an advanced feature --timeout-height uint Set a block timeout height to prevent the tx from being committed past a certain height -y, --yes Skip tx broadcasting prompt confirmation

Global Flags: --chain-id string The network chain ID --home string directory for config and data (default "~/.sei") --log\_format string The logging format (json|plain) --log\_level string The logging level (trace|debug|info|warn|error|fatal|panic) --trace print out full stack trace on errors Last updated on July 1, 2024 [wasm-store](#) [weighted-vote](#)