




CHAPTER 16 - CRT-BASED LOADING2

EDIT/LOAD PLATES..... 2

LOADING PLATES 3


Chapter 16 - CRT-BASED LOADING

Use this functionality when you need to load without using RF loading.



Edit/Load Plates

- Click the Edit menu and select Load Plates.



- Select the door for the load by double clicking the Door Loc field and selecting the door associated with the load (See the following screen). The load must be Arrived and the load status must be picked or loading.

Facility ZET Door & Staging Lane Inquiry

Door Information				Staging Lane Information							
Door	Load	Load Type	Load Status	Stage Location	Load	Stop	Load/Stop Status	Load Type	Loc. Status	Loc. Description	
DR00	201413	InCustomer	Unloaded	14210AUDIT					In-Service	AUDIT LOCATION	
DR01	201172	InCustomer	Arrived	AUDIT01					Empty	AUDIT LOCATION	
DR02	201183	InCustomer	Arrived	JK-DELETE1					Empty	JK-DELETE1	
DR03	201211	InCustomer	Arrived	STG01	201154	1	Planned	OutCustomer	In-Service	Staging Loc	
DR04	200799	OutCustomer	Picked	STG02					In-Service	Staging Loc	
DR05	201603	InCustomer	Arrived	STG03	201155	1	Planned	OutCustomer	Empty	Staging Loc	
DR06	201182	OutCustomer	Planned	STG04					In-Service	Staging Loc	
DR07	200939	OutCustomer	Loading	STG05	201535	1	Planned	OutCustomer	In-Service	Staging Loc	
DR08	201601	InCustomer	Arrived	STG06					In-Service	Staging Loc	
DR09	201405	InCustomer	Arrived	STG07	201519	1	Picked	OutCustomer	In-Service	Staging Loc	
DR10	201444	InCustomer	Arrived	STG08	201549	1	Picked	OutCustomer	In-Service	Staging Loc	
DR11	201449	InCustomer	Unloaded	STG09	201451	1	Loading	OutCustomer	In-Service	Staging Loc	
DR12	201599	InCustomer	Arrived	STG09	201509	1	Planned	OutCustomer	In-Service	Staging Loc	
DR13	201450	OutCustomer	Loaded	STG09	201538	1	Planned	OutCustomer	In-Service	Staging Loc	
DR14	201134	OutCustomer	Full Release	STG10					In-Service	Staging Loc	
DR15	200913	OutCustomer	Loading	STG11	201445	1	Planned	OutCustomer	In-Service	Staging Loc	
DR16	201451	OutCustomer	Loading	STG12					Empty	Staging Loc	

Selected Door Location: Selected Stage Location: **Out of Service**

- Press the List Plates button to view the plates staged for the load.

The plates should appear on the Plates to Load tab. The Instructions tab will display any load instructions.

Facility ZET Door & Staging Lane Inquiry


Door Loc: **DR04**


Load: **200799**


Plates To Load		Instructions											
Parent Plate	Plate	Plate Status Code	Plate Status	Item	Lot Number	Serial Number	Qty	UOM	Load No	Stop No	From Plate	Location	
	000000022483835	S	Staged	100				100	200799	1	500000000041624	STG01	

Loading Plates

- To load an individual plate, select the plate entry line and right click to show the pop-up menu. Select the Load Plate menu option to load the plate.



- To select multiple plates from the grid to load, use the Windows selection functions (Ctrl key + click to select specific plates or Shift + click to select a list). Click the Load Selected Plates button  and click Yes to confirm.



When the load is complete, the load status will change to 'Loaded' and the load can be closed from the Edit/Loads screen.