



# Bug Report

<b>ID number</b>	#1
<b>Name</b>	Tooltip is displayed outside hover area
<b>Reporter</b>	Yana B.
<b>Submit Date</b>	17/01/2026
<b>Summary</b>	Tooltip appears outside hover area and does not hide correctly in file upload component
<b>URL</b>	https://the-internet.herokuapp.com/upload
<b>Screenshot</b>	 <p><b>File Uploader</b> Choose a file on your system and then click upload. Or, drag and drop a file into the area below.</p> <p>Выберите файл   Файл не выбран</p> <p>Upload</p> <p>Test the herokuApp upload file page.docx</p>
	 <p><b>File Uploader</b> Choose a file on your system and then click upload. Or, drag and drop a file into the area below.</p> <p>Выберите файл   Test the herokuApp upload file page</p> <p>Upload</p> <p>Файл не выбран</p>
<b>Platform</b>	Macintosh
<b>Operating System</b>	Tahoe 26.1, 25B78
<b>Browser</b>	Chrome 144.0.7559.59
<b>Severity</b>	Minor

<b>Assigned to</b>	/
<b>Priority</b>	Low

### **Description**

The tooltip in the file upload component is sometimes displayed outside the hover area and does not hide correctly when the cursor moves away.

This issue occurs in different states:

No file selected: the tooltip «No file selected» remains visible after selecting a file and moving the cursor away from the Select a file button.

After clearing a selected file: the tooltip showing the name of the previously selected (now removed) file remains visible after moving the cursor away from the Select a file button.

### **Steps to reproduce**

Scenario 1 - «No file selected»:

- > click on «Select a file»
- > Select a file
- > move the cursor away from the button

Scenario 2 - after clearing a selected file:

- > click on «Select a file»
- > select a file
- > remove the selected file (click «Cancel» in the file picker)
- > move the cursor away from the button

### **Expected result**

The tooltip appears only when hovering over the file upload button or file name and disappears immediately when the cursor leaves the hover area.

Scenario 1: the tooltip with a file name is displayed when the cursor hovers the «Select a file» button or a file name, and disappears immediately when the cursor leaves the hover area.

Scenario 2: the tooltip «No file selected» is displayed when the cursor hovers the «Select a file» button.

### **Actual result**

Scenario 1: the tooltip «No file selected» remains visible at the hover area and outside the hover area

Scenario 2: the tooltip with the name of the deleted file remains visible at the hover area and outside the hover area