

ID	Summary	Pre-conditions	#	Step	ER	AR	Priority	Severity	Environment	Attachment	Status
PROF-01	The cursor doesn't change to 'pointer' on the profile and book store pages after hovering over the 'Rows' drop-down	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page.	1	Move the cursor over the 'Rows' drop-down	Cursor is changed to 'pointer' after hovering over the 'Rows' drop-down	The cursor does not change to a 'pointer' after hovering over the active 'Rows' drop-down	Low	Low	Google Chrome, v. 130.0.6723.117	Profile. The cursor does not change to 'pointer'.png	Open
PROF-02	The cursor doesn't change to 'pointer' on the profile and book store pages after hovering over the 'loup' button in the search field	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page.	1	Move the cursor over the 'loup' button	Cursor is changed to 'pointer' after hovering over the 'loup' button	The cursor doesn't change to a 'pointer' after hovering over the loup button	Low	Low	Google Chrome, v. 130.0.6723.117	Profile. Cursor for Loup button.png	Open
PROF-03	The 'Go To Book Store', 'Delete all' and 'Delete Account' buttons are not aligned on the page to each other.	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page.	1	Pay attention to the location of the 'Go To Book Store', 'Delete all' and 'Delete Account' buttons.	The 'Go To Book Store', 'Delete all' and 'Delete Account' buttons are all on the same line	The buttons are located at different heights and are not aligned with each other and with the table	Low	Low	Google Chrome, v. 130.0.6723.117	Profile. btns.png	Open
PROF-04	The 'Log out' button is glued to the table if the display size is less than 1480px	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page.	1	Pay attention to the 'Log out' button in the upper right corner.	The 'Log out' button set bottom margin and does not stick to the bottom table	The 'Log out' button stick to the bottom table when display size is less than 1480px	Medium	Low	Google Chrome, v. 130.0.6723.117	Profile. Logout btn.png	Open
PROF-05	The 'No Rows' message is displayed in the table when the user doesn't have books	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page. 3. The user has no books.	1	Pay attention to the message in the table	Show 'No books' in the table if the user has no books.	Display 'No Row' message in the empty table when the user has no books.	Low	Minor	Google Chrome, v. 130.0.6723.117	Profile. User doesn't have books.png	Open
PROF-06	The user can enter 0 in the 'Page' field if he has no books	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page. 3. The user has no books.	1	Enter the 0 into the 'Page' field	User cannot enter 0 into the 'Page' field	The user is entered 0 into the 'Page' number, when user doesn't have any book	Low	Low	Google Chrome, v. 130.0.6723.117	Profile. Page number is 0.png	Open
PROF-07	The first book image is changed to "bookimage0.jpg" in the table when user delete first book	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page. 3. The user has at least 2 books.	1	Click the 'Trash' button (in 'Action table) for the first book			Medium	Major	Google Chrome, v. 130.0.6723.117	https://drive.google.com/file/d/128NvryG44otcc-Y_Vwe4t7asmvcp-tSIY/view?usp=drive_link	Open
			2	Click the 'Ok' button (<i>confirm delete book</i>)							
			3	Click the 'Ok' button on the 'Book deleted.' notification	A deleted book does not affect the content of other books.	The image for the top book is changed to 'bookimage0.jpg' in the table after the first book is deleted.					

ID	Summary	Pre-conditions	#	Step	ER	AR	Priority	Severity	Environment	Attachment	Status
PROF-08	The 'Delete All Books' popup appears for users without books when the 'Delete All Books' button is clicked.	1. Log in to the demoqa site (https://demoqa.com/login). 2. Open the 'Profile' page. 3. The user has no books.	1	Click the 'Delete All Books' button	The 'Delete All Books' button is disabled when user has no books.	The 'Delete All Books' pop-up window appears when a user with no books clicks the 'Delete All Books'.	Medium	Minor	Google Chrome, v. 130.0.6723.117	Profile, Delete all books.png	Open