

Para terem acesso remoto por meio de VPN à Tactis foi configurado um serviço VPN, procedo a explicar os passos:

1. Fazer download de **SoftEther VPN Client**

a. <https://www.softether-download.com/en.aspx?product=softether>

b. Fazer como na figura:

Select Software

SoftEther VPN (Freeware) ▼

Select Component

SoftEther VPN Client ▼

Select Platform

Windows ▼

Select CPU

Intel (x86 and x64) ▼

Download Files (74)

► Note: The following program uses the network functions of the operating system. Some anti-virus software or firewalls warn that such behavior might be dangerous. If your anti-virus disturbs the VPN function, add the VPN program file or the installation file to the exception list.

SoftEther VPN Client (Ver 4.32, Build 9731, beta)

Clicar
Aqui


2. Instalar o programa

a. Clicar NEXT NEXT NEXT

3. Abrir o programa e configurar a VPN

a. Clicar duas vezes em **Add VPN Connection**

b. Vai aparecer esta mensagem:



Clicar em **YES**, escolher um nome conforme as indicações (VPN, VPN2, VPN3, etc, etc) e clicar em **OK**.

c. Quando a instalação concluir clicar duas vezes em **Add VPN Connection**

d. Na janela que abriu vamos colocar os dados conforme a figura seguinte (exceto o **User Authentication Setting**):

VPN Connection Setting Name	Status	VPN Server Hostname	Virtual Hub
Add VPN Connection			

Please configure the VPN Connection Setting for VPN Server.

Setting Name:

Destination VPN Server:

Specify the host name or IP address, and the port number and the Virtual Hub on the destination VPN Server.

Host Name:

Port Number: ☐ Disable NAT-T

Virtual Hub Name:

Proxy Server as Relay:

You can connect to a VPN Server via a proxy server.

Proxy Type:
 ☒ Direct TCP/IP Connection (No Proxy)
 ☐ Connect via HTTP Proxy Server
 ☐ Connect via SOCKS Proxy Server

Server Certificate Verification Options:

☐ Always Verify Server Certificate

Virtual Network Adapter to Use:

☒ VPN Client Adapter - VPN

User Authentication Setting:

Set the user authentication information that is required when connecting to the VPN Server.

Auth Type:

User Name:

Password:

Advanced Setting of Communication:

☒ Reconnects Automatically After Disconnected

Reconnect Count: times
 Reconnect Interval: seconds

☒ Infinite Reconnects (Keep VPN Always Online)
 ☐ Use SSL 3.0 (1)

☐ Hide Status and Errors Screens
 ☐ Hide IP Address Screens

Para **User Authentication Setting** as informações são as seguintes:

Users:

- ana
- barbara
- bruno
- carina
- diogo
- fabio
- francisco
- isabel
- luisa
- marcia
- mario

Senha:

- tac123tis-

A senha pode ser mudada por clicar em **“Change Password”**.

Caso se esqueçam da password peçam-me para fazer reset por favor.

Em princípio isto conclui a configuração do programa e devemos receber um IP **“192.168.70.X”**
Desta forma podemos aceder aos computadores dentro da rede local da TACTIS.

Podemos usar **RDP (WIN + R > mstsc.exe)** para fazer conexão aos nossos computadores por exemplo.