

## 1 Quick Start

### Install the Immerseum VRSimulator


1. **Make sure your Unity project meets the requirements for the Immerseum VRSimulator ('Requirements and Supported Devices' in the on-line documentation).**  
Please be sure to install the [SteamVR Plugin v. 1.1.1](#) (or higher) and [Oculus Utilities for Unity v.1.8](#) (or higher). Both are required for the VR Simulator to function, even if you're only targeting one HMD with your project.
2. **Download the Immerseum VRSimulator.**
3. **Extract the ZIP file to your hard drive.**




#### Best Practice

Remember where you extracted the ZIP file - you'll have to find the extracted folder to import the VR Simulator into Unity.

4. **Navigate to the folder where you extracted the ZIP file.** You should see the file:  
`vr-simulator-RC-1.0.unitypackage`.
5. **In Unity, open your project (or create a new project).**




8. **Select Assets > Import Package > Custom Package...**



9. Find the folder where you extracted the ZIP file. Select the file named: **VRSimulator-RC-1.0.unitypackage** and click **Open**.

10. You should now see the **\_ImmerseumSDK** folder in your Unity project's Assets. This is where the VRSimulator resides, where you can find its prefabs, scripts, and sample scenes.



11. Drag the **[VRSimulator]** prefab from **\_ImmerseumSDK / Prefabs** into your scene, and just hit "Play!"

## Open a Sample Scene

The **VRSimulator** comes packaged with sample scenes which you can find in:

```
Assets /  
    _ImmerseumSDK /  
        2_ExampleScenes /
```

## Add the VRSimulator to Your VR Scene

1. First, make sure your scene Hierarchy contains a -compatible camera rig:

- the **SteamVR**: [CameraRig] prefab, and/or;
- the Oculus camera rig, using either:


- the **Oculus:OVRCameraRig** prefab, or;
- the **Oculus:OVRPlayerController** prefab, or;

## You Should Know...

By default, you can find the camera rig prefabs in the following locations:

**SteamVR:** Assets / SteamVR / Prefabs /

**Oculus:** Assets / OVR / Prefabs /



## You Should Know...

If your scene contains one active SteamVR camera rig and one active Oculus camera rig, then the VR Simulator will automatically use the SteamVR camera rig when simulating an HMD unless you configure the HMD Simulator's **Camera Rig** property.

2. From your project's Assets folder, find the **[VR Simulator]** prefab:


Assets/

\_ImmerseumSDK/

Prefabs/

[VR Simulator]

3. Drag the **[VR Simulator]** prefab into your scene Hierarchy.



And that's it! The VR Simulator is now set up, and you can either use it right out of the box (just hit **Play**) or **Configure the VR Simulator** ('**Configuring the VR Simulator**' in the on-line documentation) however you'd like.