

ShareVR Unity Plugin v0.3


Welcome to ShareVR Unity SDK v0.3. Thanks for taking time trying out our plugin. The quick start tutorial will help you quickly setup our plugin. If you have any question, please don't hesitate to contact us at team@sharevr.io

Getting Started

ShareVR requires the SteamVR plugin loaded in your project

Import ShareVR and Load the Example Scene

- Make sure you have [SteamVR](#) plugin in your project
- Import the ShareVR Unity Plugin (currently distributed as a separate UnityPackage)
- Under Assets/ShareVR/Scenes/ open the example scene
- Hit play then you should be able to start testing
 - By default, the recording can be started and stopped by pressing the X key in your keyboard. We provided other mapping options including some that use the Vive Controllers. You can change them in the ShareVR gameobject. We also have an easy to use voice command system setup if you would like to use your own voice to control the recording.
 - **Press X key to start record.** Once you started recording, a ShareVRCameraRig game object will be instantiated with a visible camera model (you can toggle the model display on/off and change the scale of the model in the ShareVR gameobject). You should be able to see the camera started following you and the little green light on the camera indicates it's recording now.
 - Feel free to move around and teleport. The ShareVRCameraRig smoothly follows you as you move.
 - **Press X again to stop recording.** A video file will be created in the "ShareVR" folder under current Windows user's Documents folder. The path to the file will also output to the console window.




- You can record as many times as you want and each session will create a separate video file.

Apply ShareVR to Your Own Game


Our goal is make our ShareVR Unity plugin easy-to-use yet still adaptive and customizable so that it could fit well in to your own application. Here's an example of how apply ShareVR to the SteamVR InteractionSystem example scene.

- Open SteamVR interaction system example scene located at: Assets/SteamVR/InteractionSystem/Samples/Scenes/Interactions_Example
- To use ShareVR, you just need to proceed with the two step below.
 1. Under Assets/ShareVR/Prefabs/, drag the ShareVR gameobject to anywhere in the scene hierarchy.
 2. Click the ShareVR gameobject in the scene hierarchy. Reference the target gameobject that you want the spectator camera to track and record by dragging the target gameobject into "Player Head Game Object".
 3. (optional) If you are using the avatar ("ShareVR/Show Player Avatar" checked), you need to make sure the main camera ignores the avatar so that the avatar body won't occludes with your main camera. Simply find your main camera (in the InteractionSystem example, it's located at Player/SteamVRObjecs/VRCamera) and uncheck "IgnoreInMainCamera" in the Culling Mask list.
- Now you are done with the quick setup. Hit play and you should be able to record just like our example scene.

Note that We have some additional options listed below if you want to customize the plugin to better fit into your game. We kept all the available options in the ShareVR gameobject to make it easier to find. Below are the available options with description:



- *Show Camera Model* - toggles whether or not a 3D model of the recording camera will be shown. Useful if you want to see where the camera is.
- *Camera Model Scale* - If you are using the camera model, this adjusts the scale of the model so it won't be too small or big.
- *Show Player Avatar* - toggles whether or not a player avatar will be shown in the scene. We currently have a generic free avatar for you to use if you don't have an avatar for the player. Note that you can easily replace it to any 3D model you like. Please contact us if you have any specific need for the avatar.
- *Avatar Scale* - adjusts the scale of the avatar
- *Avatar Offset* - adjusts the offset between the avatar to your main player (the Player Head Game Object). Change this if the avatar appears to be off.
- *Toggle Recording Input* - use this to change your desired key mapping that triggers the start / stop recording event.
- *Use Voice Command* - check this if you want to use our voice command system to control the recording event. When enabled, simply say "Start Recording" and "Stop Recording" to start and stop an capture session.
- *Player Head Game Object* - reference your main target gameobject here and the ShareVRCameraRig will track and record it. You cannot leave this empty as it will cause error.
- *Player Hand Transforms* - (optional) if you are using the avatar and would like the hand of the avatar to track your Vive Controllers, reference your hand gameobject here otherwise it's fine to leave it blank.
- *Show Debug Message* - use this to track the status of the plugin. Debug messages will be shown in your Unity Editor Console
- *Camera Follow Method* - use this to control the way capture camera follows the main target
- *ShareVR Video Format* - change it if you want to record with a different resolution or frame rate. The default is 720p at 30 FPS to balance between video quality and performance. We are working hard optimizing our infrastructure to reduce performance cost.
- *Save Folder* - Specify the path where you want the captured video file saved. Leave it blank will trigger the default option which is under ShareVR folder in your system's Documents folder.
- *Upload File Online* - check this if you want your video automatically upload to our cloud server. A URL to your file will be provided in the console after the upload. Note that by default anyone with the link can view the video online.




Release History

Unity SDK v0.3


Release on 4/23/2017

New Features


- **AWS File Upload and Hosting** - Want to share your awesome in-game recording? Simply check *Upload File Online* option in ShareVR gameobject and your file will be automatically uploaded to our Amazon S3 server! You will see an URL to your file posted in the Unity Console after the upload is done. Note that the uploaded video file is readable to everyone with the link. Your will still have a local copy of the video file even with the file upload option on.



- **Additional Camera Follow Regime** - We are adding more camera following regimes! In SDK v0.3 we added a new smooth orbit option that you can choose in the ShareVR gameobject in addition to the fixed angle camera.




- **User Defined Save Folder** - By default, your captured video file will be saved at ShareVR folder under your current user's Document folder. You will see a full path output in the Console once you finished a recording. From SDK v0.3 and above, we now allow your to customize your own file save directory in the ShareVR gameobject. If you leave it blank, it will automatically go back to the default option.



Bug Fix and Improvements

- Fixed an issue that will cause ShareVR to crash when new game scene is loaded. Now ShareVR game objects will automatically be added to *DontDestroyOnLoad* which protects them from being unloaded when loading new game scenes.



- Fixed a bug in live plane render texture that will lead to an annoying arbitrary render texture shown in front of user.
- Fixed a bug related to game layer settings. Unity does not support passing game layer settings in Unity Package so we added a layer checking script that automatically make sure the layer setting is consistent.

Unity SDK v0.2

Release on 4/15/2017

New Features

- **Voice Command** - Having trouble deciding which key should you map to our control? Well, time to say good bye to keys. In SDK v0.2, we have configured a voice command system powered by IBM Watson Cloud Service. Simply check *Use Voice Command* and speak. Below are a list of available voice commands:
 - *[Start Recording]* - Starts a new recording
 - *[Stop Recording]* - Ends an active recording

Bug Fix and Improvements

- **Significantly reduced render cost during recording** - We spotted a bug in SDK v0.1 that trigger a catastrophic [pipeline stall](#) during recording. Fixing this bug allows us to improve the recording performance by a stunning **~70%** (more details below)!
- **Significantly improved frame rate performance** - No more fluctuating frame rates while recording! Now the frame rate will stay stabilized without big spikes in the rendering time will usually cause jitter in VR.

Profiling Data

Below are detailed Unity Profiling results. We tested SDK v0.1 and v0.2 on a normal HD recording setting (720p@30FPS) in SteamVR's interaction system example scene.


Improved Rendering Time

With the help of the powerful Unity Profiler, we can easily estimate the additional rendering time that our plugin used during recording. We measured the baseline rendering time with ShareVR in standby mode (*not recording*). In this case, the rendering time are mostly the time it takes to render the game scene itself. We then measured the worst possible rendering length after initialization (*the first few large spikes*). With calculating the difference between these two measurements, we now have a good estimate of how much additional rendering time does our ShareVR plugin added while recording.

We observed our rendering time during recording dropped from *13.67ms* to *4.20ms* which gives us an estimated performance gain of **~69.28%**. Note that this data is taken at the *worst possible spot* which means that the averaged rendering time that ShareVR need during recording will be below *4.20ms*.

Stabilized Frame Rate

In addition to rendering time improvement, it's also obvious that the frame rate is now way more stable than SDK v0.1. The main reason behind that is the pipeline stall problem. In SDK v0.1 our recording coroutine will cause pipeline stall which forces CPU and GPU to sync event with each other. It's costly operation that will lead to significantly increased rendering time. After our fix, the CPU-GPU sync will be managed by SteamVR and Unity which delivers a smooth frame rate.



ShareVR

4/23/2017