

NAME

ovn-ctl – Open Virtual Network northbound daemon lifecycle utility

SYNOPSIS

ovn-ctl [*options*] *command* [-- *extra_args*]

DESCRIPTION

This program is intended to be invoked internally by Open Virtual Network startup scripts. System administrators should not normally invoke it directly.

COMMANDS

start_northd
start_controller
start_controller_vtep
start_ic
stop_northd
stop_controller
stop_controller_vtep
stop_ic
restart_northd
restart_controller
restart_controller_vtep
restart_ic
promote_ovnnb
promote_ovnsb
demote_ovnnb
demote_ovnsb
status_ovnnb
status_ovnsb
start_ovsdb
start_nb_ovsdb
start_sb_ovsdb
stop_ovsdb
stop_nb_ovsdb
stop_sb_ovsdb
restart_ovsdb
run_nb_ovsdb
run_sb_ovsdb
promote_ic_nb
promote_ic_sb
demote_ic_nb
demote_ic_sb
status_ic_nb
status_ic_sb
start_ic_ovsdb
start_ic_nb_ovsdb
start_ic_sb_ovsdb
stop_ic_ovsdb
stop_ic_nb_ovsdb
stop_ic_sb_ovsdb
restart_ic_ovsdb
run_ic_nb_ovsdb
run_ic_sb_ovsdb

OPTIONS

--ovn-northd-priority=*NICE*

```
--ovn-northd-wrapper=WRAPPER
--ovn-controller-priority=NICE
--ovn-controller-wrapper=WRAPPER
--ovn-ic-priority=NICE
--ovn-ic-wrapper=WRAPPER
--ovsdb-nb-wrapper=WRAPPER
--ovsdb-sb-wrapper=WRAPPER
--ovn-user=USER:GROUP
-h | --help
```

FILE LOCATION OPTIONS

```
--db-sock=SOCKET
--db-nb-file=FILE
--db-sb-file=FILE
--db-nb-schema=FILE
--db-sb-schema=FILE
--db-sb-create-insecure-remote=yes|no
--db-nb-create-insecure-remote=yes|no
--db-ic-nb-file=FILE
--db-ic-sb-file=FILE
--db-ic-nb-schema=FILE
--db-ic-sb-schema=FILE
--db-ic-sb-create-insecure-remote=yes|no
--db-ic-nb-create-insecure-remote=yes|no
--db-nb-config-file=FILE
--db-sb-config-file=FILE
--db-ic-nb-config-file=FILE
--db-ic-sb-config-file=FILE
--db-sb-relay-config-file=FILE
--ovn-controller-ssl-key=KEY
--ovn-controller-ssl-cert=CERT
--ovn-controller-ssl-ca-cert=CERT
--ovn-controller-ssl-bootstrap-ca-cert=CERT
```

PROTOCOL, CIPHER AND CIPHERSUITE OPTIONS

```
--ovn-controller-ssl-protocols=PROTOCOLS
--ovn-ic-ssl-protocols=PROTOCOLS
--ovn-northd-ssl-protocols=PROTOCOLS
--ovn-nb-db-ssl-protocols=PROTOCOLS
--ovn-sb-db-ssl-protocols=PROTOCOLS
--ovn-ic-nb-db-ssl-protocols=PROTOCOLS
--ovn-ic-sb-db-ssl-protocols=PROTOCOLS
```

```
--ovn-controller-ssl-ciphers=CIPHERS
--ovn-ic-ssl-ciphers=CIPHERS
--ovn-northd-ssl-ciphers=CIPHERS
--ovn-nb-db-ssl-ciphers=CIPHERS
--ovn-sb-db-ssl-ciphers=CIPHERS
--ovn-ic-nb-db-ssl-ciphers=CIPHERS
--ovn-ic-sb-db-ssl-ciphers=CIPHERS
--ovn-controller-ssl-ciphersuites=CIPHERSUITES
--ovn-ic-ssl-ciphersuites=CIPHERSUITES
--ovn-northd-ssl-ciphersuites=CIPHERSUITES
--ovn-nb-db-ssl-ciphersuites=CIPHERSUITES
--ovn-sb-db-ssl-ciphersuites=CIPHERSUITES
--ovn-ic-nb-db-ssl-ciphersuites=CIPHERSUITES
--ovn-ic-sb-db-ssl-ciphersuites=CIPHERSUITES
```

ADDRESS AND PORT OPTIONS

```
--db-nb-sync-from-addr=IP ADDRESS
--db-nb-sync-from-port=PORT NUMBER
--db-nb-sync-from-proto=PROTO
--db-sb-sync-from-addr=IP ADDRESS
--db-sb-sync-from-port=PORT NUMBER
--db-sb-sync-from-proto=PROTO
--db-ic-nb-sync-from-addr=IP ADDRESS
--db-ic-nb-sync-from-port=PORT NUMBER
--db-ic-nb-sync-from-proto=PROTO
--db-ic-sb-sync-from-addr=IP ADDRESS
--db-ic-sb-sync-from-port=PORT NUMBER
--db-ic-sb-sync-from-proto=PROTO
--ovn-northd-nb-db=PROTO:IP ADDRESS: PORT..
--ovn-northd-sb-db=PROTO:IP ADDRESS: PORT..
--ovn-ic-nb-db=PROTO:IP ADDRESS: PORT..
--ovn-ic-sb-db=PROTO:IP ADDRESS: PORT..
```

CLUSTERING OPTIONS

```
--db-nb-cluster-local-addr=IP ADDRESS
--db-nb-cluster-local-port=PORT NUMBER
--db-nb-cluster-local-proto=PROTO (tcp/ssl)
--db-nb-cluster-remote-addr=IP ADDRESS
--db-nb-cluster-remote-port=PORT NUMBER
--db-nb-cluster-remote-proto=PROTO (tcp/ssl)
--db-nb-election-timer=Timeout in milliseconds
--db-sb-cluster-local-addr=IP ADDRESS
```


ic-sb-active.conf

If present, this file should hold the url to connect to the active Interconnection Southbound DB server

tcp:x.x.x.x:6646

ovn-ic-db-params.conf

If present, this file should hold the database url parameters to be passed to ovn-ic.

--ic-nb-db=tcp:x.x.x.x:6645 --ic-sb-db=tcp:x.x.x.x:6646

RUNNING OVN DB SERVERS WITHOUT DETACHING

ovn-ctl run_nb_ovsdb

This command runs the OVN nb ovsdb-server without passing the **detach** option, making it to block until ovsdb-server exits. This command will be useful for starting the OVN nb ovsdb-server in a container.

ovn-ctl run_sb_ovsdb

This command runs the OVN sb ovsdb-server without passing the **detach** option, making it to block until ovsdb-server exits. This command will be useful for starting the OVN sb ovsdb-server in a container.

ovn-ctl run_ic_nb_ovsdb

This command runs the OVN IC-NB ovsdb-server without passing the **detach** option, making it to block until ovsdb-server exits. This command will be useful for starting the OVN IC-NB ovsdb-server in a container.

ovn-ctl run_ic_sb_ovsdb

This command runs the OVN IC-SB ovsdb-server without passing the **detach** option, making it to block until ovsdb-server exits. This command will be useful for starting the OVN IC-SB ovsdb-server in a container.

EXAMPLE USAGE

Run ovn-controller on a host already running OVS

ovn-ctl start_controller

Run ovn-northd on a host already running OVS

ovn-ctl start_northd

All-in-one OVS+OVN for testing

ovs-ctl start --system-id="random"

ovn-ctl start_northd

ovn-ctl start_controller

Promote and demote ovsdb servers

ovn-ctl promote_ovnnb

ovn-ctl promote_ovnsb

ovn-ctl --db-nb-sync-from-addr=x.x.x.x --db-nb-sync-from-port=6641 --db-nb-probe-interval-to-active=60000 demote_ovnnb

ovn-ctl --db-sb-sync-from-addr=x.x.x.x --db-sb-sync-from-port=6642 --db-sb-probe-interval-to-active=60000 demote_ovnsb

Creating a clustered db on 3 nodes with IPs x.x.x.x, y.y.y.y and z.z.z.z

Starting OVN ovsdb servers and ovn-northd on the node with IP x.x.x.x

ovn-ctl --db-nb-addr=x.x.x.x --db-nb-create-insecure-remote=yes --db-sb-addr=x.x.x.x --db-sb-create-insecure-remote=yes --db-nb-cluster-local-addr=x.x.x.x --db-sb-cluster-local-addr=x.x.x.x --ovn-northd-nb-db=tcp:x.x.x.x:6641, tcp:y.y.y.y:6641, tcp:z.z.z.z:6641 --ovn-northd-sb-db=tcp:x.x.x.x:6642, tcp:y.y.y.y:6642, tcp:z.z.z.z:6642 start_northd

Starting OVN ovsdb-servers and ovn-northd on the node with IP y.y.y.y and joining the cluster started at x.x.x.x

```
# ovn-ctl --db-nb-addr=y.y.y.y --db-nb-create-insecure-remote=yes --db-sb-addr=y.y.y.y
--db-sb-create-insecure-remote=yes --db-nb-cluster-local-addr=y.y.y.y --db-sb-cluster-lo-
cal-addr=y.y.y.y --db-nb-cluster-remote-addr=x.x.x.x --db-sb-cluster-remote-addr=x.x.x.x
--ovn-northd-nb-db=tcp:x.x.x.x:6641,tcp:y.y.y.y:6641,tcp:z.z.z.z:6641
--ovn-northd-sb-db=tcp:x.x.x.x:6642,tcp:y.y.y.y:6642,tcp:z.z.z.z:6642 start_northd
```

Starting OVN ovsdb-servers and ovn-northd on the node with IP z.z.z.z and joining the cluster started at x.x.x.x

```
# ovn-ctl --db-nb-addr=z.z.z.z --db-nb-create-insecure-remote=yes --db-nb-cluster-lo-
cal-addr=z.z.z.z --db-sb-addr=z.z.z.z --db-sb-create-insecure-remote=yes --db-sb-cluster-lo-
cal-addr=z.z.z.z --db-nb-cluster-remote-addr=x.x.x.x --db-sb-cluster-remote-addr=x.x.x.x
--ovn-northd-nb-db=tcp:x.x.x.x:6641,tcp:y.y.y.y:6641,tcp:z.z.z.z:6641
--ovn-northd-sb-db=tcp:x.x.x.x:6642,tcp:y.y.y.y:6642,tcp:z.z.z.z:6642 start_northd
```

Passing ssl keys when starting OVN dbs will supersede the default ssl values in db

Starting standalone ovn db server passing SSL/TLS certificates

```
# ovn-ctl --ovn-nb-db-ssl-key=/etc/ovn/ovnnb-privkey.pem
--ovn-nb-db-ssl-cert=/etc/ovn/ovnnb-cert.pem --ovn-nb-db-ssl-ca-cert=/etc/ovn/cacert.pem
--ovn-sb-db-ssl-key=/etc/ovn/ovnsb-privkey.pem --ovn-sb-db-ssl-cert=/etc/ovn/ovnsb-cert.pem
--ovn-sb-db-ssl-ca-cert=/etc/ovn/cacert.pem start_northd
```

Avoiding automatic clustered OVN database schema upgrade

If you desire more control over clustered DB schema upgrade, you can opt-out of automatic on-start upgrade attempts with **--no-db-cluster-schema-upgrade**.

Start OVN NB and SB clustered databases on host with IP x.x.x.x without schema upgrade

```
# ovn-ctl start_nb_ovsdb --db-nb-cluster-local-addr=x.x.x.x --no-db-cluster-schema-upgrade
# ovn-ctl start_sb_ovsdb --db-sb-cluster-local-addr=x.x.x.x --no-db-cluster-schema-upgrade
```

Trigger clustered DB schema upgrade manually

```
# ovsdb-client convert unix:/var/run/ovn/ovnnb_db.sock /usr/local/share/ovn/ovn-nb.ovsschema #
ovsdb-client convert unix:/var/run/ovn/ovnsb_db.sock /usr/local/share/ovn/ovn-sb.ovsschema
```