

Ev3Dev

0.1.1

Generated by Doxygen 1.8.11

Contents

1	Hierarchical Index	1
1.1	Class Hierarchy	1
2	Class Index	3
2.1	Class List	3
3	File Index	5
3.1	File List	5
4	Class Documentation	7
4.1	ev3::Action Class Reference	7
4.1.1	Detailed Description	8
4.1.2	Member Enumeration Documentation	9
4.1.2.1	ActionType	9
4.1.3	Constructor & Destructor Documentation	9
4.1.3.1	Action(CommandsVector commands, ActionType type)	9
4.1.3.2	Action(CommandsVector commands)	9
4.1.3.3	Action(ActionType type)	9
4.1.4	Member Function Documentation	10
4.1.4.1	getActionPrototype()	10
4.1.4.2	getString()	10
4.1.4.3	getType()	10
4.1.4.4	isExecuted()	10
4.1.4.5	isFinished()	10
4.1.4.6	setCommands(CommandsVector commands)	10

4.1.4.7	setEndCondition(EndCondition condition)	11
4.1.5	Member Data Documentation	11
4.1.5.1	_endCondition	11
4.2	ev3::ActionDriveDistance Class Reference	11
4.2.1	Detailed Description	12
4.2.2	Constructor & Destructor Documentation	12
4.2.2.1	ActionDriveDistance(int distance)	12
4.2.2.2	ActionDriveDistance(CommandsVector commands, int distance)	12
4.2.3	Member Function Documentation	12
4.2.3.1	getActionPrototype()	12
4.2.3.2	getDistance()	13
4.2.3.3	getString() override	13
4.3	ev3::ActionDriveForever Class Reference	13
4.3.1	Detailed Description	14
4.3.2	Constructor & Destructor Documentation	14
4.3.2.1	ActionDriveForever(bool forward=true)	14
4.3.2.2	ActionDriveForever(CommandsVector commands, bool forward=true)	14
4.3.3	Member Function Documentation	14
4.3.3.1	getActionPrototype()	14
4.3.3.2	getString() override	15
4.3.3.3	isForward()	15
4.4	ev3::ActionRepeat Class Reference	15
4.4.1	Detailed Description	16
4.4.2	Constructor & Destructor Documentation	16
4.4.2.1	ActionRepeat(StoredActions actions, unsigned int n)	16
4.4.3	Member Function Documentation	16
4.4.3.1	getString()	16
4.5	ev3::ActionRotate Class Reference	16
4.5.1	Detailed Description	17
4.5.2	Constructor & Destructor Documentation	17

4.5.2.1	ActionRotate(int rotation)	17
4.5.2.2	ActionRotate(CommandsVector commands, int rotation)	17
4.5.3	Member Function Documentation	18
4.5.3.1	getActionPrototype()	18
4.5.3.2	getRotation()	18
4.5.3.3	getString() override	18
4.6	ev3::ActionRotateRandDirection Class Reference	18
4.6.1	Detailed Description	19
4.6.2	Constructor & Destructor Documentation	19
4.6.2.1	ActionRotateRandDirection(int rotation)	19
4.6.2.2	ActionRotateRandDirection(CommandsVector commands, int rotation)	19
4.6.3	Member Function Documentation	19
4.6.3.1	execute() override	19
4.6.3.2	getActionPrototype()	20
4.6.3.3	getString() override	20
4.7	ev3::ActionStop Class Reference	20
4.7.1	Detailed Description	21
4.7.2	Constructor & Destructor Documentation	21
4.7.2.1	ActionStop(CommandsVector commands)	21
4.7.3	Member Function Documentation	21
4.7.3.1	getActionPrototype()	21
4.7.3.2	getString() override	21
4.8	ev3::Agent Class Reference	22
4.9	ev3::Behaviour Class Reference	22
4.9.1	Detailed Description	24
4.9.2	Member Enumeration Documentation	24
4.9.2.1	BehaviourType	24
4.9.3	Constructor & Destructor Documentation	24
4.9.3.1	Behaviour(BehaviourType type, BehaviourStates states)	24
4.9.3.2	Behaviour(BehaviourType type)	24

4.9.4	Member Function Documentation	24
4.9.4.1	getPrototype()	24
4.9.4.2	getString()	25
4.9.4.3	react(Event::EventType type)	25
4.9.4.4	setMeasurements(Measurements measurements)	25
4.9.4.5	setReactionStates(BehaviourStates reactionStates)	25
4.9.4.6	setStates(BehaviourStates states)	25
4.9.4.7	setStopState(BehaviourState state)	26
4.10	ev3::BehaviourDriveOnSquare Class Reference	26
4.10.1	Member Function Documentation	26
4.10.1.1	getPrototype() override	26
4.10.1.2	getString() override	27
4.11	ev3::BehaviourExploreRandom Class Reference	27
4.11.1	Member Function Documentation	27
4.11.1.1	getPrototype() override	27
4.11.1.2	getString() override	28
4.12	ev3::BehaviourState Class Reference	28
4.13	ev3dev::button Class Reference	28
4.14	ev3::CircularBuffer< T > Class Template Reference	29
4.15	ev3dev::color_sensor Class Reference	29
4.16	ev3::ColorUtils Class Reference	30
4.17	ev3::Command Class Reference	31
4.17.1	Detailed Description	32
4.17.2	Member Function Documentation	32
4.17.2.1	getString()	32
4.18	ev3::CommandMotor Class Reference	32
4.18.1	Detailed Description	33
4.18.2	Constructor & Destructor Documentation	33
4.18.2.1	CommandMotor(Motor &motor)	33
4.18.3	Member Function Documentation	33

4.18.3.1	getMotor()	33
4.19	ev3::CommandMotorReset Class Reference	34
4.19.1	Detailed Description	34
4.19.2	Constructor & Destructor Documentation	34
4.19.2.1	CommandMotorReset(Motor &motor)	34
4.20	ev3::CommandMotorRunForever Class Reference	35
4.20.1	Detailed Description	35
4.20.2	Constructor & Destructor Documentation	35
4.20.2.1	CommandMotorRunForever(Motor &motor)	35
4.21	ev3::CommandMotorSetSpeed Class Reference	36
4.21.1	Detailed Description	36
4.21.2	Constructor & Destructor Documentation	36
4.21.2.1	CommandMotorSetSpeed(Motor &motor, int value)	36
4.22	ev3::CommandMotorSetSpeedRegEnabled Class Reference	37
4.22.1	Detailed Description	37
4.22.2	Constructor & Destructor Documentation	37
4.22.2.1	CommandMotorSetSpeedRegEnabled(Motor &motor, bool value)	37
4.23	ev3::CommandMotorSetStopMode Class Reference	38
4.23.1	Detailed Description	38
4.23.2	Member Enumeration Documentation	39
4.23.2.1	StopMode	39
4.23.3	Constructor & Destructor Documentation	39
4.23.3.1	CommandMotorSetStopMode(Motor &motor, StopMode mode)	39
4.24	ev3::CommandMotorStop Class Reference	39
4.24.1	Detailed Description	40
4.24.2	Constructor & Destructor Documentation	40
4.24.2.1	CommandMotorStop(Motor &motor)	40
4.25	ev3::CommandSensor Class Reference	40
4.25.1	Detailed Description	41
4.25.2	Constructor & Destructor Documentation	41

4.25.2.1	CommandSensor(Sensor &sensor)	41
4.25.3	Member Function Documentation	41
4.25.3.1	getSensor()	41
4.26	ev3::Communication Class Reference	41
4.27	ev3::CommUtils Class Reference	42
4.28	ev3dev::dc_motor Class Reference	42
4.29	ev3dev::device Class Reference	43
4.30	ev3::Devices Class Reference	44
4.31	ev3::Event Class Reference	45
4.32	ev3::EventAction Class Reference	46
4.33	ev3::EventQueue Class Reference	46
4.34	ev3::EventSensorWatch Class Reference	47
4.35	ev3dev::gyro_sensor Class Reference	47
4.36	ev3dev::i2c_sensor Class Reference	48
4.37	ev3dev::infrared_sensor Class Reference	49
4.38	ev3dev::large_motor Class Reference	49
4.39	ev3dev::lcd Class Reference	50
4.40	ev3dev::led Class Reference	50
4.41	ev3::LedControl Class Reference	52
4.42	ev3dev::lego_port Class Reference	52
4.43	ev3dev::light_sensor Class Reference	53
4.44	ev3::Logger Class Reference	54
4.45	ev3::Master Class Reference	54
4.46	ev3dev::medium_motor Class Reference	55
4.47	ev3::Message Class Reference	55
4.48	ev3::Motor Class Reference	56
4.49	ev3dev::motor Class Reference	56
4.50	ev3::CommUtils::NetworkNode Struct Reference	58
4.51	ev3dev::power_supply Class Reference	59
4.52	ev3::Queue< T > Class Template Reference	59

4.53	ev3dev::remote_control Class Reference	60
4.54	ev3::Robot Class Reference	60
4.55	ev3::RobotModelA Class Reference	61
4.56	ev3::RobotState Class Reference	62
4.57	ev3::RobotStateActive Class Reference	63
4.58	ev3::RobotStateIdle Class Reference	63
4.59	ev3::RobotStatePanic Class Reference	64
4.60	ev3::RobotStatePaused Class Reference	64
4.61	ev3::RobotStateWorking Class Reference	65
4.62	ev3dev::sensor Class Reference	66
4.63	ev3::Sensor Class Reference	67
4.64	ev3dev::servo_motor Class Reference	68
4.65	ev3::SignalHandler Class Reference	69
4.66	ev3dev::sound Class Reference	69
4.67	ev3dev::sound_sensor Class Reference	69
4.68	ev3dev::touch_sensor Class Reference	70
4.69	ev3dev::ultrasonic_sensor Class Reference	71
5	File Documentation	73
5.1	/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Action.h File Reference	73
5.1.1	Detailed Description	74
5.1.2	Typedef Documentation	74
5.1.2.1	StoredActions	74
5.2	/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Behaviour.h File Reference	74
5.2.1	Detailed Description	74
5.3	/home/panda/Dokumenty/Repos/Ev3Dev/include/action/BehaviourState.h File Reference	75
5.3.1	Detailed Description	75
	Index	77

Chapter 1

Hierarchical Index

1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

ev3::Action	7
ev3::ActionDriveDistance	11
ev3::ActionDriveForever	13
ev3::ActionRepeat	15
ev3::ActionRotate	16
ev3::ActionRotateRandDirection	18
ev3::ActionStop	20
ev3::Agent	22
ev3::Behaviour	22
ev3::BehaviourDriveOnSquare	26
ev3::BehaviourExploreRandom	27
ev3::BehaviourState	28
ev3dev::button	28
ev3::CircularBuffer< T >	29
ev3::CircularBuffer< std::string >	29
ev3::ColorUtils	30
ev3::Command	31
ev3::CommandMotor	32
ev3::CommandMotorReset	34
ev3::CommandMotorRunForever	35
ev3::CommandMotorSetSpeed	36
ev3::CommandMotorSetSpeedRegEnabled	37
ev3::CommandMotorSetStopMode	38
ev3::CommandMotorStop	39
ev3::CommandSensor	40
ev3::Communication	41
ev3::CommUtils	42
ev3dev::device	43
ev3dev::dc_motor	42
ev3dev::led	50
ev3dev::lego_port	52
ev3dev::motor	56
ev3dev::large_motor	49
ev3dev::medium_motor	55

ev3dev::power_supply	59
ev3dev::sensor	66
ev3dev::color_sensor	29
ev3dev::gyro_sensor	47
ev3dev::i2c_sensor	48
ev3dev::infrared_sensor	49
ev3dev::light_sensor	53
ev3dev::sound_sensor	69
ev3dev::touch_sensor	70
ev3dev::ultrasonic_sensor	71
ev3dev::servo_motor	68
ev3::Devices	44
ev3::Event	45
ev3::EventAction	46
ev3::EventSensorWatch	47
ev3::EventQueue	46
ev3dev::lcd	50
ev3::LedControl	52
ev3::Logger	54
ev3::Master	54
ev3::Message	55
ev3::Motor	56
ev3::CommUtils::NetworkNode	58
ev3::Queue< T >	59
ev3::Queue< ev3::Message >	59
ev3dev::remote_control	60
ev3::Robot	60
ev3::RobotModelA	61
ev3::RobotState	62
ev3::RobotStateActive	63
ev3::RobotStateIdle	63
ev3::RobotStatePanic	64
ev3::RobotStatePaused	64
ev3::RobotStateWorking	65
ev3::Sensor	67
ev3::SignalHandler	69
ev3dev::sound	69

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

ev3::Action	Base class for all Action controlling classes	7
ev3::ActionDriveDistance	Implements Robot simple task to drive straight for a given distance	11
ev3::ActionDriveForever	Implements Robot simple task to drive straight forever	13
ev3::ActionRepeat	Stores many Actions in a vector and executes them in loop	15
ev3::ActionRotate	Implements Robot simple task to rotate a given angle, while not driving	16
ev3::ActionRotateRandDirection	Implements Robot simple task to rotate a random angle	18
ev3::ActionStop	Implements Robot simple task to stop all active motors	20
ev3::Agent	22
ev3::Behaviour	Base class for all defined behaviours	22
ev3::BehaviourDriveOnSquare	26
ev3::BehaviourExploreRandom	27
ev3::BehaviourState	28
ev3dev::button	28
ev3::CircularBuffer< T >	29
ev3dev::color_sensor	29
ev3::ColorUtils	30
ev3::Command	Base class for all command controlling classes	31
ev3::CommandMotor	Base class for all motor controlling commands	32
ev3::CommandMotorReset	Calls <code>reset()</code> method of containing Motor	34
ev3::CommandMotorRunForever	Calls <code>run_forever()</code> method of containing Motor	35
ev3::CommandMotorSetSpeed	Call <code>set_speed_sp()</code> method of containing Motor	36
ev3::CommandMotorSetSpeedRegEnabled	Calls <code>set_speed_regulation_enabled()</code> method of containing Motor	37

ev3::CommandMotorSetStopMode	
Calls <code>set_stop_command()</code> method of containing Motor	38
ev3::CommandMotorStop	
Calls <code>stop()</code> method of containing Motor	39
ev3::CommandSensor	
Base class for all sensor controlling commands	40
ev3::Communication	41
ev3::CommUtils	42
ev3dev::dc_motor	42
ev3dev::device	43
ev3::Devices	44
ev3::Event	45
ev3::EventAction	46
ev3::EventQueue	46
ev3::EventSensorWatch	47
ev3dev::gyro_sensor	47
ev3dev::i2c_sensor	48
ev3dev::infrared_sensor	49
ev3dev::large_motor	49
ev3dev::lcd	50
ev3dev::led	50
ev3::LedControl	52
ev3dev::lego_port	52
ev3dev::light_sensor	53
ev3::Logger	54
ev3::Master	54
ev3dev::medium_motor	55
ev3::Message	55
ev3::Motor	56
ev3dev::motor	56
ev3::CommUtils::NetworkNode	58
ev3dev::power_supply	59
ev3::Queue< T >	59
ev3dev::remote_control	60
ev3::Robot	60
ev3::RobotModelA	61
ev3::RobotState	62
ev3::RobotStateActive	63
ev3::RobotStateIdle	63
ev3::RobotStatePanic	64
ev3::RobotStatePaused	64
ev3::RobotStateWorking	65
ev3dev::sensor	66
ev3::Sensor	67
ev3dev::servo_motor	68
ev3::SignalHandler	69
ev3dev::sound	69
ev3dev::sound_sensor	69
ev3dev::touch_sensor	70
ev3dev::ultrasonic_sensor	71

Chapter 3

File Index

3.1 File List

Here is a list of all documented files with brief descriptions:

/home/panda/Dokumenty/Repos/Ev3Dev/include/action/ Action.h	
Contains all Action classes	73
/home/panda/Dokumenty/Repos/Ev3Dev/include/action/ Behaviour.h	
Contains all Behaviour classes	74
/home/panda/Dokumenty/Repos/Ev3Dev/include/action/ BehaviourState.h	
Contains BehaviourState class	75
/home/panda/Dokumenty/Repos/Ev3Dev/include/action/ Command.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/action/ CommandMotor.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/action/ CommandSensor.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/communication/ Communication.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/communication/ CommUtils.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/communication/ Event.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/communication/ Message.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/control/ LedControl.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ ev3dev.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/master/ Agent.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/master/ Master.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/ Devices.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/ Motor.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/ Robot.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/ RobotModelA.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/ RobotState.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/ Sensor.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ CircularBuffer.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ ColorUtils.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ EventQueue.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ Logger.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ Queue.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ SignalHandler.h	??
/home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ Utils.h	??

Chapter 4


Class Documentation

4.1 ev3::Action Class Reference

Base class for all [Action](#) controlling classes.

```
#include <Action.h>
```

Inheritance diagram for ev3::Action:



Public Types

- enum [ActionType](#) {
 [NOP](#), [REPEAT](#), [DRIVE_DISTANCE](#), [ROTATE](#),
 [ROTATE_RANDOM_DIR](#), [STOP](#), [DRIVE_FOREVER](#) }
 Type of [Action](#).
- typedef std::function< bool(void) > [EndCondition](#)
 Type for lambda functions to store end of [Action](#) condition.

Public Member Functions

- [Action](#) ([CommandsVector](#) commands, [ActionType](#) type)
 Constructor with [CommandsVector](#) and [ActionType](#) parameters.
- [Action](#) ([CommandsVector](#) commands)
 Constructor with [CommandsVector](#) parameter.
- [Action](#) ([ActionType](#) type)
 Constructor with [ActionType](#) parameter.
- virtual [~Action](#) ()
 Default destructor.
- virtual void [execute](#) ()
 Executes stored [Commands](#) in a sequence.

- virtual bool `isFinished ()`
Check if [Action](#) condition is fulfilled.
- virtual bool `isExecuted ()`
Check if action was executed.
- virtual std::string `getActionPrototype ()`
Generate std::string prototype for [Action](#).
- virtual std::string `getString ()`
Get human-readable [Action](#) name.
- void `setCommands (CommandsVector commands)`
Set [Commands](#) to be executed.
- void `setEndCondition (EndCondition condition)`
Set end condition for [Action](#).
- [ActionType](#) `getType ()`
Get current [Action](#) type.

Static Public Attributes

- static const std::string `EMPTY_PROTO`
String for empty [Action](#) prototype.

Protected Attributes

- [ActionType](#) `_type`
[Action](#) type.
- [CommandsVector](#) `_commands`
Vector of [Commands](#).
- [EndCondition](#) `_endCondition`
Lambda function defining [Action](#) end condition.
- bool `_isExecuted` = false

4.1.1 Detailed Description

Base class for all [Action](#) controlling classes.

Each [Action](#) contains of a sequence of many [Commands](#) and all of them are executed immediately, one after another. [Action](#) is valid, until specific [Event](#) occurs or its `endCondition` function returns true.

[Action](#) objects are instantiated accordingly to [Robot](#) model that uses them. Actions are predefined and cannot be dynamically created.

4.1.2 Member Enumeration Documentation

4.1.2.1 enum ev3::Action::ActionType

Type of [Action](#).

It directly points to derived class being used.

See also

[Robot::AvailableActions](#)

Enumerator

NOP No operation.

REPEAT Repeats execution of other [Actions](#).

DRIVE_DISTANCE Power [Motor](#) to reach certain distance.

ROTATE Rotate [Robot](#) for given angle.

ROTATE_RANDOM_DIR Rotate for given angle, clockwise or counterclockwise at random.

STOP Stop all active motors.

DRIVE_FOREVER Drive forward or backward infinitely.

4.1.3 Constructor & Destructor Documentation

4.1.3.1 Action::Action (CommandsVector *commands*, ActionType *type*)

Constructor with CommandsVector and ActionType parameters.

Parameters

<i>commands</i>	Commands stored within this Action .
<i>type</i>	Type of Action used.

4.1.3.2 Action::Action (CommandsVector *commands*)

Constructor with CommandsVector parameter.

[Action type](#) is set to [Action::NOP](#) .

Parameters

<i>commands</i>	Commands stored within this Action .
-----------------	--

4.1.3.3 Action::Action (ActionType *type*)

Constructor with ActionType parameter.

Parameters

<i>type</i>	Type of Action used.
-------------	--------------------------------------

4.1.4 Member Function Documentation

4.1.4.1 `std::string Action::getActionPrototype ()` [virtual]

Generate `std::string` prototype for [Action](#).

Returns

Encoded [Action](#) data into `std::string`.

Reimplemented in [ev3::ActionDriveForever](#), [ev3::ActionStop](#), [ev3::ActionRotateRandDirection](#), [ev3::ActionRotate](#), and [ev3::ActionDriveDistance](#).

4.1.4.2 `std::string Action::getString ()` [virtual]

Get human-readable [Action](#) name.

Returns

String containing [Action](#) name.

Reimplemented in [ev3::ActionDriveForever](#), [ev3::ActionStop](#), [ev3::ActionRotateRandDirection](#), [ev3::ActionRotate](#), [ev3::ActionDriveDistance](#), and [ev3::ActionRepeat](#).

4.1.4.3 `Action::ActionType Action::getType ()`

Get current [Action](#) type.

Returns

ActionType value.

4.1.4.4 `bool Action::isExecuted ()` [virtual]

Check if action was executed.

Returns

True if action was already executed, false otherwise.

4.1.4.5 `bool Action::isFinished ()` [virtual]

Check if [Action](#) condition is fulfilled.

Returns

Value returned from [Action::_endCondition](#).

4.1.4.6 `void Action::setCommands (CommandsVector commands)`

Set [Commands](#) to be executed.

Parameters

<i>commands</i>	CommandsVector with pointers to commands.
-----------------	---

4.1.4.7 void Action::setEndCondition (EndCondition *condition*)

Set end condition for [Action](#).

Parameters

<i>condition</i>	Lambda function returning bool value.
------------------	---------------------------------------

4.1.5 Member Data Documentation

4.1.5.1 EndCondition ev3::Action::_endCondition [protected]

Initial value:

```
= [] ()
{
    return true;
}
```

Lambda function defining [Action](#) end condition.

The documentation for this class was generated from the following files:


- /home/panda/Dokumenty/Repos/Ev3Dev/include/action/[Action.h](#)
- /home/panda/Dokumenty/Repos/Ev3Dev/src/action/Action.cpp

4.2 ev3::ActionDriveDistance Class Reference

Implements [Robot](#) simple task to drive straight for a given distance.

```
#include <Action.h>
```

Inheritance diagram for ev3::ActionDriveDistance:



Public Member Functions

- [ActionDriveDistance](#) (int distance)
Constructor with distance parameter.
- [ActionDriveDistance](#) ([CommandsVector](#) commands, int distance)
Constructor with CommandsVector and distance parameters.
- int [getDistance](#) ()
Get distance the [Robot](#) has to drive.
- virtual std::string [getActionPrototype](#) ()
Get [ActionDriveDistance](#) encoded name and its parameters.
- virtual std::string [getString](#) () override
Get [ActionDriveDistance](#) human-readable name.

Additional Inherited Members

4.2.1 Detailed Description

Implements [Robot](#) simple task to drive straight for a given distance.

4.2.2 Constructor & Destructor Documentation

4.2.2.1 [ActionDriveDistance::ActionDriveDistance](#) (int *distance*)

Constructor with distance parameter.

Parameters

<i>distance</i>	Integer value in Robot units to be driven.
-----------------	--

4.2.2.2 [ActionDriveDistance::ActionDriveDistance](#) ([CommandsVector](#) *commands*, int *distance*)

Constructor with CommandsVector and distance parameters.

Parameters

<i>commands</i>	Sequence of commands to be executed.
<i>distance</i>	Integer value in Robot units to be driven.

4.2.3 Member Function Documentation

4.2.3.1 std::string [ActionDriveDistance::getActionPrototype](#) () [virtual]

Get [ActionDriveDistance](#) encoded name and its parameters.

Returns

String with encoded name and parameters.

Reimplemented from [ev3::Action](#).

4.2.3.2 int ActionDriveDistance::getDistance ()

Get distance the [Robot](#) has to drive.

Returns

Integer value in [Robot](#) units.

4.2.3.3 std::string ActionDriveDistance::getString () [override],[virtual]

Get [ActionDriveDistance](#) human-readable name.

Returns

String with name and parameters

Reimplemented from [ev3::Action](#).

The documentation for this class was generated from the following files:


- [/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Action.h](#)
- [/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Action.cpp](#)

4.3 ev3::ActionDriveForever Class Reference

Implements [Robot](#) simple task to drive straight forever.

```
#include <Action.h>
```

Inheritance diagram for ev3::ActionDriveForever:



Public Member Functions

- [ActionDriveForever](#) (bool forward=true)
Constructor with direction parameter.
- [ActionDriveForever](#) ([CommandsVector](#) commands, bool forward=true)
Constructor with CommandsVector and direction parameter.
- virtual std::string [getActionPrototype](#) ()
Get [ActionDriveForever](#) encoded name and its parameters.
- virtual std::string [getString](#) () override
Get [ActionDriveForever](#) human-readable name.
- bool [isForward](#) ()
Return specified direction.

Additional Inherited Members

4.3.1 Detailed Description

Implements [Robot](#) simple task to drive straight forever.

4.3.2 Constructor & Destructor Documentation

4.3.2.1 [ActionDriveForever::ActionDriveForever](#) (bool *forward* = true)

Constructor with direction parameter.

Parameters

<i>forward</i>	True to drive forward, false otherwise.
----------------	---

4.3.2.2 [ActionDriveForever::ActionDriveForever](#) ([CommandsVector](#) *commands*, bool *forward* = true)

Constructor with CommandsVector and direction parameter.

Parameters

<i>forward</i>	True to drive forward, false otherwise.
----------------	---

4.3.3 Member Function Documentation

4.3.3.1 std::string [ActionDriveForever::getActionPrototype](#) () [virtual]

Get [ActionDriveForever](#) encoded name and its parameters.

Returns

String with encoded name and parameters.

Reimplemented from [ev3::Action](#).

4.3.3.2 `std::string ActionDriveForever::getString ()` `[override],[virtual]`

Get [ActionDriveForever](#) human-readable name.

Returns

String with name and parameters

Reimplemented from [ev3::Action](#).

4.3.3.3 `bool ActionDriveForever::isForward ()`

Return specified direction.

Returns

True for forward, false for backward.

The documentation for this class was generated from the following files:


- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Action.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Action.cpp`

4.4 ev3::ActionRepeat Class Reference

Stores many Actions in a vector and executes them in loop.

```
#include <Action.h>
```

Inheritance diagram for `ev3::ActionRepeat`:

**Public Member Functions**

- [ActionRepeat](#) ([StoredActions](#) actions, unsigned int n)
Constructor with StoredActions and iterations parameters.
- virtual void [execute](#) ()
Continue with executing stored Actions.
- virtual `std::string` [getString](#) ()
Return human-readable [ActionRepeat](#) name.

Additional Inherited Members

4.4.1 Detailed Description

Stores many Actions in a vector and executes them in loop.

Number of iterations is given and may be infinite.

4.4.2 Constructor & Destructor Documentation

4.4.2.1 ActionRepeat::ActionRepeat (**StoredActions** *actions*, unsigned int *n*)

Constructor with StoredActions and iterations parameters.

Parameters

<i>actions</i>	Vector of Actions to be executed in a loop.
<i>n</i>	Number of iterations. If 0 is given, loop will be infinite.

4.4.3 Member Function Documentation

4.4.3.1 std::string ActionRepeat::getString () [virtual]

Return human-readable [ActionRepeat](#) name.

Returns

String containing [Action](#) name.

Reimplemented from [ev3::Action](#).

The documentation for this class was generated from the following files:


- /home/panda/Dokumenty/Repos/Ev3Dev/include/action/[Action.h](#)
- /home/panda/Dokumenty/Repos/Ev3Dev/src/action/Action.cpp

4.5 ev3::ActionRotate Class Reference

Implements [Robot](#) simple task to rotate a given angle, while not driving.

```
#include <Action.h>
```

Inheritance diagram for ev3::ActionRotate:



Public Member Functions

- [ActionRotate](#) (int rotation)
Constructor with rotation parameter in degrees.
- [ActionRotate](#) ([CommandsVector](#) commands, int rotation)
Constructor with CommandsVector and rotation parameters.
- int [getRotation](#) ()
Get [Robot](#) rotation.
- virtual std::string [getActionPrototype](#) ()
Get [ActionRotate](#) encoded name and its parameters.
- virtual std::string [getString](#) () override
Get [ActionRotate](#) human-readable name.

Protected Attributes

- int [_rotation](#)
Angle of rotation in degrees for the [Robot](#).

Additional Inherited Members

4.5.1 Detailed Description

Implements [Robot](#) simple task to rotate a given angle, while not driving.

Rotation is made in place.

4.5.2 Constructor & Destructor Documentation

4.5.2.1 [ActionRotate::ActionRotate](#) (int rotation)

Constructor with rotation parameter in degrees.

Parameters

<i>rotation</i>	Number of degrees to rotate. Positive value rotates clockwise.
-----------------	--

4.5.2.2 [ActionRotate::ActionRotate](#) ([CommandsVector](#) commands, int rotation)

Constructor with CommandsVector and rotation parameters.

Parameters

<i>commands</i>	Sequence of commands to be executed.
<i>rotation</i>	Integer value of Robot rotation in degrees.

4.5.3 Member Function Documentation

4.5.3.1 `std::string ActionRotate::getActionPrototype ()` [virtual]

Get [ActionRotate](#) encoded name and its parameters.

Returns

String with encoded name and parameters.

Reimplemented from [ev3::Action](#).

Reimplemented in [ev3::ActionRotateRandDirection](#).

4.5.3.2 `int ActionRotate::getRotation ()`

Get [Robot](#) rotation.

Returns

Integer value of rotation in degrees.

4.5.3.3 `std::string ActionRotate::getString ()` [override],[virtual]

Get [ActionRotate](#) human-readable name.

Returns

String with name and parameters

Reimplemented from [ev3::Action](#).

Reimplemented in [ev3::ActionRotateRandDirection](#).

The documentation for this class was generated from the following files:


- [/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Action.h](#)
- [/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Action.cpp](#)

4.6 [ev3::ActionRotateRandDirection](#) Class Reference

Implements [Robot](#) simple task to rotate a random angle.

```
#include <Action.h>
```

Inheritance diagram for [ev3::ActionRotateRandDirection](#):



Public Member Functions

- [ActionRotateRandDirection](#) (int rotation)
Constructor with rotation parameter in degrees.
- [ActionRotateRandDirection](#) ([CommandsVector](#) commands, int rotation)
Constructor with CommandsVector and rotation parameters.
- virtual std::string [getActionPrototype](#) ()
Get [ActionRotateRandDirection](#) encoded name and its parameters.
- virtual std::string [getString](#) () override
Get [ActionRotateRandDirection](#) human-readable name.
- virtual void [execute](#) () override

Additional Inherited Members

4.6.1 Detailed Description

Implements [Robot](#) simple task to rotate a random angle.

Rotation is performed in place. Maximum angle in degrees is passed via constructor argument.

4.6.2 Constructor & Destructor Documentation

4.6.2.1 ActionRotateRandDirection::ActionRotateRandDirection (int *rotation*)

Constructor with rotation parameter in degrees.

Parameters

<i>rotation</i>	Upper limit of degrees to rotate randomly. Positive value rotates clockwise.
-----------------	--

4.6.2.2 ActionRotateRandDirection::ActionRotateRandDirection ([CommandsVector](#) *commands*, int *rotation*)

Constructor with CommandsVector and rotation parameters.

Parameters

<i>commands</i>	Sequence of commands to be executed.
<i>rotation</i>	Upper limit of degrees to rotate randomly. Positive value rotates clockwise.

4.6.3 Member Function Documentation

4.6.3.1 void ActionRotateRandDirection::execute () [[override](#)], [[virtual](#)]

See also

[Action::execute](#)

Reimplemented from [ev3::Action](#).

4.6.3.2 `std::string ActionRotateRandDirection::getActionPrototype ()` `[virtual]`

Get [ActionRotateRandDirection](#) encoded name and its parameters.

Returns

String with encoded name and parameters.

Reimplemented from [ev3::ActionRotate](#).

4.6.3.3 `std::string ActionRotateRandDirection::getString ()` `[override],[virtual]`

Get [ActionRotateRandDirection](#) human-readable name.

Returns

String with name and parameters

Reimplemented from [ev3::ActionRotate](#).

The documentation for this class was generated from the following files:


- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Action.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Action.cpp`

4.7 ev3::ActionStop Class Reference

Implements [Robot](#) simple task to stop all active motors.

```
#include <Action.h>
```

Inheritance diagram for `ev3::ActionStop`:



Public Member Functions

- [ActionStop](#) ()
Default constructor.
- [ActionStop](#) ([CommandsVector](#) commands)
Constructor with CommandsVector parameter.
- virtual std::string [getActionPrototype](#) ()
Get [ActionStop](#) encoded name and its parameters.
- virtual std::string [getString](#) () override
Get [ActionStop](#) human-readable name.

Additional Inherited Members

4.7.1 Detailed Description

Implements [Robot](#) simple task to stop all active motors.

4.7.2 Constructor & Destructor Documentation

4.7.2.1 [ActionStop::ActionStop](#) ([CommandsVector](#) commands)

Constructor with CommandsVector parameter.

Parameters

<i>commands</i>	Sequence of commands to be executed.
-----------------	--------------------------------------

4.7.3 Member Function Documentation

4.7.3.1 std::string [ActionStop::getActionPrototype](#) () [virtual]

Get [ActionStop](#) encoded name and its parameters.

Returns

String with encoded name and parameters.

Reimplemented from [ev3::Action](#).

4.7.3.2 std::string [ActionStop::getString](#) () [override],[virtual]

Get [ActionStop](#) human-readable name.

Returns

String with name and parameters

Reimplemented from [ev3::Action](#).

The documentation for this class was generated from the following files:

- [/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Action.h](#)
- [/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Action.cpp](#)

4.8 ev3::Agent Class Reference

Public Member Functions

- unsigned int **getId** ()
- void **setId** (const unsigned int id)
- unsigned int **getCommId** ()
- void **setCommId** (const unsigned int commId)
- void **processMessage** ([Message](#) *message, [Message](#) *retMessage)
- void **updateLastMessage** ([Message](#) *message)
- void **setBehaviour** ([SharedPtrBehaviour](#) behaviour)
- void **setMeasurement** ([Measurements](#) measurements)

The documentation for this class was generated from the following files:


- [/home/panda/Dokumenty/Repos/Ev3Dev/include/master/Agent.h](#)
- [/home/panda/Dokumenty/Repos/Ev3Dev/src/master/Agent.cpp](#)

4.9 ev3::Behaviour Class Reference

Base class for all defined behaviours.

```
#include <Behaviour.h>
```

Inheritance diagram for ev3::Behaviour:



Public Types

- enum [BehaviourType](#) { [CUSTOM](#), [DRIVE_ON_SQUARE](#), [EXPLORE_RANDOM](#) }
- Type of [Behaviour](#).*

Public Member Functions

- [Behaviour](#) ()=default
Default constructor.
- [Behaviour](#) ([BehaviourType](#) type, [BehaviourStates](#) states)
Constructor with type and states vector parameters.
- [Behaviour](#) ([BehaviourType](#) type)
Constructor with behaviour type.
- void [setStates](#) ([BehaviourStates](#) states)
Available states setter.
- void [setReactionStates](#) ([BehaviourStates](#) reactionStates)
Special reaction states which occur when event is fired.
- void [setStopState](#) ([BehaviourState](#) state)
Special stop state, used mainly to get precise sensor measurements.
- void [setMeasurements](#) ([Measurements](#) measurements)
Sensor which measurements will be required.
- virtual [StringVector](#) [getPrototype](#) ()
Get [Behaviour](#) encoded name and its parameters.
- virtual [std::string](#) [getString](#) ()
Get [Behaviour](#) human-readable name.
- virtual void [process](#) ()
Updates behaviour in every iteration.
- void [stop](#) ()
Stops [Behaviour](#) execution definately.
- void [pause](#) ()
Pauses [Behaviour](#) execution until it's resumed.
- void [resume](#) ()
Resumes paused [Behaviour](#).
- void [start](#) ()
Starts [Behaviour](#) execution.
- void [react](#) ([Event::EventType](#) type)
Performs special actions based on [Event](#) passed.

Static Public Member Functions

- static [StringVector](#) [getParameters](#) ([StringVector](#) proto)

Protected Attributes

- [BehaviourType](#) [_type](#)
Type of [Behaviour](#).
- [BehaviourState](#) [_currentState](#)
Currently processed [Behaviour](#).
- [BehaviourState](#) [_stopState](#)
Special stop state for measurements and accurate action execution.
- [BehaviourStates](#) [_states](#)
Vector with all [Behaviour](#) available states.
- [BehaviourStates](#) [_reactionStates](#)
Vector with all reaction states, occuring after specific events.
- [Measurements](#) [_measurements](#)
Vector of all [Sensor](#) ids that will be measured.
- bool [_active](#) = false
Specified whether [Behaviour](#) is currently active or not.

4.9.1 Detailed Description

Base class for all defined behaviours.

It's responsible for maintaining active actions in a form of a state machine as well as keep track of sensors' measurements.

4.9.2 Member Enumeration Documentation

4.9.2.1 enum `ev3::Behaviour::BehaviourType`

Type of [Behaviour](#).

Enumerator

CUSTOM Custom, user-defined behaviour.

DRIVE_ON_SQUARE Follow square-shaped route.

EXPLORE_RANDOM Drive in a direction and rotate randomly.

4.9.3 Constructor & Destructor Documentation

4.9.3.1 `Behaviour::Behaviour (BehaviourType type, BehaviourStates states)`

Constructor with type and states vector parameters.

Parameters

<i>type</i>	Behaviour type.
<i>states</i>	Vector of available Behaviour states.

4.9.3.2 `Behaviour::Behaviour (BehaviourType type)`

Constructor with behaviour type.

Parameters

<i>type</i>	Behaviour type.
-------------	---------------------------------

4.9.4 Member Function Documentation

4.9.4.1 `StringVector Behaviour::getPrototype () [virtual]`

Get [Behaviour](#) encoded name and its parameters.

Returns

StringVector with encoded name and parameters as its members.

Reimplemented in [ev3::BehaviourExploreRandom](#), and [ev3::BehaviourDriveOnSquare](#).

4.9.4.2 `std::string Behaviour::getString ()` [virtual]

Get [Behaviour](#) human-readable name.

Returns

String with name and parameters

Reimplemented in [ev3::BehaviourExploreRandom](#), and [ev3::BehaviourDriveOnSquare](#).

4.9.4.3 `void Behaviour::react (Event::EventType type)`

Performs special actions based on [Event](#) passed.

Parameters

<i>type</i>	Event type that will be processed.
-------------	--

4.9.4.4 `void Behaviour::setMeasurements (Measurements measurements)`

[Sensor](#) which measurements will be required.

Parameters

<i>measurements</i>	Vector of sensor types.
---------------------	-------------------------

4.9.4.5 `void Behaviour::setReactionStates (BehaviourStates reactionStates)`

Special reaction states which occur when event is fired.

Parameters

<i>reactionStates</i>	Vector of reaction states for this Behaviour .
-----------------------	--

4.9.4.6 `void Behaviour::setStates (BehaviourStates states)`

Available states setter.

Parameters

<i>states</i>	Vector of states for this Behaviour .
---------------	---

4.9.4.7 void Behaviour::setStopState (BehaviourState state)

Special stop state, used mainly to get precise sensor measurements.

Parameters


<i>state</i>	BehaviourState object for stop state.
--------------	---

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/action/[Behaviour.h](#)
- /home/panda/Dokumenty/Repos/Ev3Dev/src/action/Behaviour.cpp

4.10 ev3::BehaviourDriveOnSquare Class Reference

Inheritance diagram for ev3::BehaviourDriveOnSquare:



Public Member Functions

- **BehaviourDriveOnSquare** (unsigned int side, bool turningRight)
- **BehaviourDriveOnSquare** ([BehaviourStates](#) states, unsigned int side, bool turningRight)
- StringVector [getPrototype](#) () override
Get [Behaviour](#) encoded name and its parameters.
- virtual std::string [getString](#) () override
Get [Behaviour](#) human-readable name.

Additional Inherited Members

4.10.1 Member Function Documentation

4.10.1.1 StringVector BehaviourDriveOnSquare::getPrototype () [override], [virtual]

Get [Behaviour](#) encoded name and its parameters.

Returns

StringVector with encoded name and parameters as its members.

Reimplemented from [ev3::Behaviour](#).

4.10.1.2 `std::string BehaviourDriveOnSquare::getString ()` `[override],[virtual]`

Get [Behaviour](#) human-readable name.

Returns

String with name and parameters


Reimplemented from [ev3::Behaviour](#).

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Behaviour.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Behaviour.cpp`

4.11 ev3::BehaviourExploreRandom Class Reference

Inheritance diagram for `ev3::BehaviourExploreRandom`:



Public Member Functions

- **BehaviourExploreRandom** ([BehaviourStates](#) states)
- `StringVector getPrototype ()` `override`
Get [Behaviour](#) encoded name and its parameters.
- `virtual std::string getString ()` `override`
Get [Behaviour](#) human-readable name.

Additional Inherited Members

4.11.1 Member Function Documentation

4.11.1.1 `StringVector BehaviourExploreRandom::getPrototype ()` `[override],[virtual]`

Get [Behaviour](#) encoded name and its parameters.

Returns

StringVector with encoded name and parameters as its members.

Reimplemented from [ev3::Behaviour](#).

4.11.1.2 `std::string BehaviourExploreRandom::getString ()` `[override],[virtual]`

Get [Behaviour](#) human-readable name.

Returns

String with name and parameters

Reimplemented from [ev3::Behaviour](#).

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Behaviour.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Behaviour.cpp`

4.12 `ev3::BehaviourState` Class Reference

Public Member Functions

- **BehaviourState** (const [BehaviourState](#) &)=default
- **BehaviourState** ([SharedPtrAction](#) action, unsigned int nextState, bool isStopState=false)
- **BehaviourState** ([SharedPtrAction](#) action, unsigned int nextState, ReactionsTransitions reactions)
- unsigned int **process** ()
- [SharedPtrAction](#) **getAction** ()
- void **setNextState** (const unsigned int next)
- bool **isStopState** ()
- void **setReactions** (ReactionsTransitions reactions)
- int **getReaction** (Event::EventType type)

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/BehaviourState.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/BehaviourState.cpp`

4.13 `ev3dev::button` Class Reference

Public Member Functions

- **button** (int bit)
- bool **pressed** () const
- bool **process** ()

Static Public Member Functions

- static bool **process_all** ()

Public Attributes

- std::function< void(bool)> **onclick**

Static Public Attributes

- static **button** **back**
- static **button** **left**
- static **button** **right**
- static **button** **up**
- static **button** **down**
- static **button** **enter**

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.14 ev3::CircularBuffer< T > Class Template Reference

Public Member Functions


- **CircularBuffer** (unsigned int limit)
- void **push** (T object)
- bool **contain** (T object)

The documentation for this class was generated from the following file:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/Utils/CircularBuffer.h

4.15 ev3dev::color_sensor Class Reference

Inheritance diagram for ev3dev::color_sensor:



Public Member Functions

- **color_sensor** (address_type address=INPUT_AUTO)
- int **reflected_light_intensity** ()
- int **ambient_light_intensity** ()
- int **color** ()
- int **red** ()
- int **green** ()
- int **blue** ()

Static Public Attributes

- static const std::string **mode_col_reflect** { "COL-REFLECT" }
- static const std::string **mode_col_ambient** { "COL-AMBIENT" }
- static const std::string **mode_col_color** { "COL-COLOR" }
- static const std::string **mode_ref_raw** { "REF-RAW" }
- static const std::string **mode_rgb_raw** { "RGB-RAW" }

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.16 ev3::ColorUtils Class Reference

Public Types

- typedef std::string **colorCode**

Static Public Member Functions

- static void **printColorTest** ()

Static Public Attributes

- static const colorCode **BLACK** {"\033[30m"}
- static const colorCode **RED** {"\033[31m"}
- static const colorCode **GREEN** {"\033[32m"}
- static const colorCode **YELLOW** {"\033[33m"}
- static const colorCode **BLUE** {"\033[34m"}
- static const colorCode **MAGENTA** {"\033[35m"}
- static const colorCode **CYAN** {"\033[36m"}
- static const colorCode **WHITE** {"\033[37m"}
- static const colorCode **BLACK_BOLD** {"\033[30;1m"}
- static const colorCode **RED_BOLD** {"\033[31;1m"}
- static const colorCode **GREEN_BOLD** {"\033[32;1m"}
- static const colorCode **YELLOW_BOLD** {"\033[33;1m"}
- static const colorCode **BLUE_BOLD** {"\033[34;1m"}
- static const colorCode **MAGENTA_BOLD** {"\033[35;1m"}
- static const colorCode **CYAN_BOLD** {"\033[36;1m"}
- static const colorCode **WHITE_BOLD** {"\033[37;1m"}
- static const colorCode **BLACK_FAINT** {"\033[30;2m"}
- static const colorCode **RED_FAINT** {"\033[31;2m"}
- static const colorCode **GREEN_FAINT** {"\033[32;2m"}
- static const colorCode **YELLOW_FAINT** {"\033[33;2m"}
- static const colorCode **BLUE_FAINT** {"\033[34;2m"}
- static const colorCode **MAGENTA_FAINT** {"\033[35;2m"}
- static const colorCode **CYAN_FAINT** {"\033[36;2m"}
- static const colorCode **WHITE_FAINT** {"\033[37;2m"}
- static const colorCode **RESET** {"\033[39;0m"}

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/utils/ColorUtils.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/utils/ColorUtils.cpp

4.17 ev3::Command Class Reference

Base class for all command controlling classes.

```
#include <Command.h>
```

Inheritance diagram for ev3::Command:



Public Member Functions

- [Command](#) ()
Default constructor.
- virtual void [execute](#) ()
Execute device specific command.
- virtual std::string [getString](#) ()
Return [Command](#)'s name.

Protected Attributes

- `std::string _debugInfo = ""`
String containing [Command](#)'s name.

4.17.1 Detailed Description

Base class for all command controlling classes.

Each [Command](#) class encapsulates basic motor or sensor operation.

4.17.2 Member Function Documentation

4.17.2.1 `std::string Command::getString ()` [virtual]

Return [Command](#)'s name.

Returns

The documentation for this class was generated from the following files:


- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Command.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/Command.cpp`

4.18 `ev3::CommandMotor` Class Reference

Base class for all motor controlling commands.

```
#include <CommandMotor.h>
```

Inheritance diagram for `ev3::CommandMotor`:



Public Member Functions

- [CommandMotor](#) ([Motor](#) &motor)
Constructor with `ev3dev::motor` parameter.
- [Motor getMotor](#) ()
Get motor associated with [Command](#).

Protected Attributes

- const std::string [SPEED_REGULATION_ON](#) = "on"
Command parameter to turn speed regulation on a [Motor](#) on.
- const std::string [SPEED_REGULATION_OFF](#) = "off"
Command parameter to turn speed regulation on a [Motor](#) off.
- [Motor _motor](#)
Motor on which this [CommandMotor](#) will be executed.

4.18.1 Detailed Description

Base class for all motor controlling commands.

See also

[ev3dev::motor](#)

4.18.2 Constructor & Destructor Documentation

4.18.2.1 CommandMotor::CommandMotor ([Motor](#) & *motor*)

Constructor with [ev3dev::motor](#) parameter.

Parameters

<i>motor</i>	Motor to execute CommandMotor on.
--------------	---

4.18.3 Member Function Documentation

4.18.3.1 [Motor](#) CommandMotor::getMotor ()

Get motor associated with [Command](#).

Returns

[Motor](#) class object.

The documentation for this class was generated from the following files:


- /home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandMotor.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandMotor.cpp

4.19 ev3::CommandMotorReset Class Reference

Calls `reset ()` method of containing [Motor](#).

```
#include <CommandMotor.h>
```

Inheritance diagram for `ev3::CommandMotorReset`:



Public Member Functions

- [CommandMotorReset](#) ([Motor](#) &motor)
Constructor with `ev3dev::motor` parameter.
- void [execute](#) () override
Perform `reset ()` method on [Motor](#).

Additional Inherited Members

4.19.1 Detailed Description

Calls `reset ()` method of containing [Motor](#).

4.19.2 Constructor & Destructor Documentation

4.19.2.1 CommandMotorReset::CommandMotorReset ([Motor](#) & *motor*)

Constructor with `ev3dev::motor` parameter.

Parameters

<i>motor</i>	Motor to execute CommandMotor on.
--------------	---

The documentation for this class was generated from the following files:


- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandMotor.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandMotor.cpp`

4.20 ev3::CommandMotorRunForever Class Reference

Calls `run_forever()` method of containing [Motor](#).

```
#include <CommandMotor.h>
```

Inheritance diagram for `ev3::CommandMotorRunForever`:



Public Member Functions

- [CommandMotorRunForever](#) ([Motor](#) &motor)
Constructor with [ev3dev::motor](#) parameter.
- void [execute](#) () override
Perform `run_forever()` method on [Motor](#).

Additional Inherited Members

4.20.1 Detailed Description

Calls `run_forever()` method of containing [Motor](#).

4.20.2 Constructor & Destructor Documentation

4.20.2.1 CommandMotorRunForever::CommandMotorRunForever ([Motor](#) & *motor*)

Constructor with [ev3dev::motor](#) parameter.

Parameters

<i>motor</i>	Motor to execute CommandMotor on.
--------------	---

The documentation for this class was generated from the following files:


- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandMotor.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandMotor.cpp`

4.21 ev3::CommandMotorSetSpeed Class Reference

Call `set_speed_sp()` method of containing [Motor](#).

```
#include <CommandMotor.h>
```

Inheritance diagram for `ev3::CommandMotorSetSpeed`:



Public Member Functions

- [CommandMotorSetSpeed](#) ([Motor](#) &motor, int value)
Constructor with [ev3dev::motor](#) parameter.
- void [execute](#) () override
Perform `set_speed_sp()` method on [Motor](#).

Additional Inherited Members

4.21.1 Detailed Description

Call `set_speed_sp()` method of containing [Motor](#).

4.21.2 Constructor & Destructor Documentation

4.21.2.1 CommandMotorSetSpeed::CommandMotorSetSpeed ([Motor](#) & motor, int value)

Constructor with [ev3dev::motor](#) parameter.

Parameters

<i>motor</i>	Motor to execute CommandMotor on.
<i>value</i>	Speed value in tacho pulses per second.

Warning

Speed regulation must be turned on for this to take effect.

See also

[CommandMotorSetSpeedRegEnabled](#)

The documentation for this class was generated from the following files:


- /home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandMotor.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandMotor.cpp

4.22 ev3::CommandMotorSetSpeedRegEnabled Class Reference

Calls `set_speed_regulation_enabled()` method of containing [Motor](#).

```
#include <CommandMotor.h>
```

Inheritance diagram for `ev3::CommandMotorSetSpeedRegEnabled`:



Public Member Functions

- [CommandMotorSetSpeedRegEnabled](#) ([Motor](#) &motor, bool value)
Constructor with `ev3dev::motor` parameter.
- void [execute](#) () override
Perform `set_speed_regulation_enabled()` on [Motor](#).

Additional Inherited Members

4.22.1 Detailed Description

Calls `set_speed_regulation_enabled()` method of containing [Motor](#).

4.22.2 Constructor & Destructor Documentation

4.22.2.1 CommandMotorSetSpeedRegEnabled::CommandMotorSetSpeedRegEnabled ([Motor](#) & motor, bool value)

Constructor with `ev3dev::motor` parameter.

Parameters

<i>motor</i>	Motor to execute CommandMotor on.
<i>value</i>	If true, turn speed regulation on, false to turn it off.

The documentation for this class was generated from the following files:


- /home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandMotor.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandMotor.cpp

4.23 ev3::CommandMotorSetStopMode Class Reference

Calls `set_stop_command()` method of containing [Motor](#).

```
#include <CommandMotor.h>
```

Inheritance diagram for `ev3::CommandMotorSetStopMode`:



Public Types

- enum [StopMode](#) { [COAST](#), [BRAKE](#), [HOLD](#) }
Stop modes for motors.

Public Member Functions

- [CommandMotorSetStopMode](#) ([Motor](#) &motor, [StopMode](#) mode)
Constructor with `ev3dev::motor` parameter.
- void [execute](#) () override
Perform `set_stop_command()` method on [Motor](#).

Additional Inherited Members

4.23.1 Detailed Description

Calls `set_stop_command()` method of containing [Motor](#).

4.23.2 Member Enumeration Documentation

4.23.2.1 enum ev3::CommandMotorSetStopMode::StopMode

Stop modes for motors.

Enumerator

COAST No voltage. [Motor](#) slowly stops.

BRAKE Passive braking. [Motor](#) stops faster.

HOLD Active braking. Hardly prevent motor from any movement.

4.23.3 Constructor & Destructor Documentation

4.23.3.1 CommandMotorSetStopMode::CommandMotorSetStopMode ([Motor](#) & *motor*, **StopMode** *mode*)

Constructor with [ev3dev::motor](#) parameter.

Parameters

<i>motor</i>	Motor to execute CommandMotor on.
<i>mode</i>	Stop mode chosen from StopMode .

The documentation for this class was generated from the following files:


- /home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandMotor.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandMotor.cpp

4.24 ev3::CommandMotorStop Class Reference

Calls `stop()` method of containing [Motor](#).

```
#include <CommandMotor.h>
```

Inheritance diagram for `ev3::CommandMotorStop`:



Public Member Functions

- [CommandMotorStop](#) ([Motor](#) &motor)
Constructor with [ev3dev::motor](#) parameter.
- void [execute](#) () override
Perform `stop()` method on [Motor](#).

Additional Inherited Members

4.24.1 Detailed Description

Calls `stop()` method of containing [Motor](#).

4.24.2 Constructor & Destructor Documentation

4.24.2.1 [CommandMotorStop::CommandMotorStop](#) ([Motor](#) & *motor*)

Constructor with [ev3dev::motor](#) parameter.

Parameters

<i>motor</i>	Motor to execute CommandMotor on.
--------------	---

The documentation for this class was generated from the following files:


- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandMotor.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandMotor.cpp`

4.25 [ev3::CommandSensor](#) Class Reference

Base class for all sensor controlling commands.

```
#include <CommandSensor.h>
```

Inheritance diagram for [ev3::CommandSensor](#):



Public Member Functions

- [CommandSensor](#) ([Sensor](#) &sensor)
Constructor with [ev3dev::sensor](#) parameter.
- [Sensor](#) [getSensor](#) ()
Get sensor associated with [Command](#).

Protected Attributes

- [Sensor_sensor](#)
Sensor on which this [CommandSensor](#) will be executed.

4.25.1 Detailed Description

Base class for all sensor controlling commands.

See also

[ev3dev::sensor](#)

4.25.2 Constructor & Destructor Documentation

4.25.2.1 `CommandSensor::CommandSensor (Sensor & sensor)`

Constructor with [ev3dev::sensor](#) parameter.

Parameters

<i>sensor</i>	Sensor to execute CommandSensor on.
---------------	---

4.25.3 Member Function Documentation

4.25.3.1 `Sensor CommandSensor::getSensor ()`

Get sensor associated with [Command](#).

Returns

[Sensor](#) class object.

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/CommandSensor.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/action/CommandSensor.cpp`

4.26 ev3::Communication Class Reference

Public Member Functions

- `std::thread createThread (Queue< Message > *sendQueue, Queue< Message > *receiveQueue, bool isMaster=false)`
- `void run (Queue< Message > *sendQueue, Queue< Message > *receiveQueue, bool isMaster=false)`

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/communication/Communication.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/communication/Communication.cpp`

4.27 ev3::CommUtils Class Reference

Classes

- struct [NetworkNode](#)

Public Member Functions


- int **preparePassiveSocket** (unsigned int portNumber)
- int **sendMessage** (unsigned int socket, unsigned int port, [Message](#) &message, std::string &proto, bool isMaster, unsigned int repeat=SENT_MESSAGE_COPIES)
- int **receiveMessage** (unsigned int socket, [Message](#) &msg, [NetworkNode](#) &sender)
- int **receiveMessageDelay** (unsigned int socket, [Message](#) &msg, [NetworkNode](#) &sender, unsigned int msDelay=DEFAULT_RECEIVE_DELAY)

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/communication/CommUtils.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/communication/CommUtils.cpp

4.28 ev3dev::dc_motor Class Reference

Inheritance diagram for ev3dev::dc_motor:



Public Member Functions

- **dc_motor** (address_type address=OUTPUT_AUTO)
- auto **set_command** (std::string v) -> decltype(*this)
- mode_set **commands** () const
- std::string **driver_name** () const
- int **duty_cycle** () const
- int **duty_cycle_sp** () const
- auto **set_duty_cycle_sp** (int v) -> decltype(*this)
- std::string **polarity** () const
- auto **set_polarity** (std::string v) -> decltype(*this)
- std::string **address** () const
- int **ramp_down_sp** () const
- auto **set_ramp_down_sp** (int v) -> decltype(*this)
- int **ramp_up_sp** () const
- auto **set_ramp_up_sp** (int v) -> decltype(*this)
- mode_set **state** () const
- auto **set_stop_command** (std::string v) -> decltype(*this)
- mode_set **stop_commands** () const
- int **time_sp** () const
- auto **set_time_sp** (int v) -> decltype(*this)
- void **run_forever** ()
- void **run_timed** ()
- void **run_direct** ()
- void **stop** ()

Static Public Attributes

- static const std::string **command_run_forever** { "run-forever" }
- static const std::string **command_run_timed** { "run-timed" }
- static const std::string **command_run_direct** { "run-direct" }
- static const std::string **command_stop** { "stop" }
- static const std::string **polarity_normal** { "normal" }
- static const std::string **polarity_inversed** { "inversed" }
- static const std::string **stop_command_coast** { "coast" }
- static const std::string **stop_command_brake** { "brake" }

Protected Attributes

- std::string **_port_name**


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.29 ev3dev::device Class Reference

Inheritance diagram for ev3dev::device:



Public Member Functions

- bool **connect** (const std::string &dir, const std::string &pattern, const std::map< std::string, std::set< std::string >> &match) noexcept
- bool **connected** () const
- int **device_index** () const
- int **get_attr_int** (const std::string &name) const
- void **set_attr_int** (const std::string &name, int value)
- std::string **get_attr_string** (const std::string &name) const
- void **set_attr_string** (const std::string &name, const std::string &value)
- std::string **get_attr_line** (const std::string &name) const
- mode_set **get_attr_set** (const std::string &name, std::string *pCur=nullptr) const
- std::string **get_attr_from_set** (const std::string &name) const

Protected Attributes

- `std::string _path`
- `int _device_index = -1`

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp`

4.30 ev3::Devices Class Reference

Public Types

- `typedef std::map< ev3dev::port_type, Motor > MotorsVector`
- `typedef std::map< ev3dev::port_type, Sensor > SensorsVector`
- `typedef std::vector< std::pair< ev3dev::port_type, ev3dev::device_type > > RequiredDevices`
- `typedef std::map< ev3dev::port_type, SensorValue > SensorStatus`

Public Member Functions

- `bool checkDevices (RequiredDevices &devices)`
- `void update ()`
- `void addListener (Sensor::SensorType type)`
- `void removeListener (Sensor::SensorType type)`
- `Motor getMotor (ev3dev::port_type port)`
- `Sensor getSensor (ev3dev::port_type port)`
- `void setSafetyTouchSensor (ev3dev::port_type port)`
- `void setProximitySensor (ev3dev::port_type port)`
- `void stopAllDevices ()`

Static Public Member Functions

- `static Devices * getInstance ()`
- `static void destroy ()`

Static Public Attributes

- `static const ev3dev::port_type PORT_ANY {"any"}`

Protected Member Functions

- `Devices (const Devices &)`
- `Devices & operator= (const Devices &)`

Protected Attributes

- `std::map< Sensor::SensorType, bool > _listeners`
- `std::map< ev3dev::port_type, int > _safetyTouchSensors`
- `std::map< ev3dev::port_type, int > _proximitySensors`
- `MotorsVector _motors`
- `SensorsVector _sensors`
- `SensorStatus _status`

Static Protected Attributes


- static `Devices * _instance = nullptr`

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/Devices.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/robot/Devices.cpp`

4.31 ev3::Event Class Reference

Inheritance diagram for `ev3::Event`:



Public Types

- enum `EventType` {
`EMPTY`, `BEHAVIOUR_START`, `BEHAVIOUR_STOP`, `SENSOR_WATCH`,
`OBSTACLE_DETECTED`, `PROXIMITY_ALERT`, `ACTION_FINISHED`, `ACTION_INTERR` }

Public Member Functions


- `Event` (`EventType` type)
- `EventType` `getType` ()
- `std::string` `getStringType` ()

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/communication/Event.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/communication/Event.cpp`

4.32 ev3::EventAction Class Reference

Inheritance diagram for ev3::EventAction:



Public Member Functions

- **EventAction** (EventType eventType, [Action::ActionType](#) actionType)
- [Action::ActionType](#) **getActionType** ()

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/communication/Event.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/communication/Event.cpp

4.33 ev3::EventQueue Class Reference

Public Member Functions

- void **push** (SharedPtrEvent message)
- SharedPtrEvent **pop** ()
- bool **empty** ()
- unsigned int **size** ()

Static Public Member Functions

- static [EventQueue](#) * **getInstance** ()
- static void **destroy** ()

Protected Member Functions

- **EventQueue** (const [EventQueue](#) &)
- [EventQueue](#) & **operator=** (const [EventQueue](#) &)

Protected Attributes

- std::queue< SharedPtrEvent > **_queue**
- std::mutex **_mutex**

Static Protected Attributes


- static [EventQueue](#) * **_instance** = nullptr

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/utils/EventQueue.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/utils/EventQueue.cpp

4.34 ev3::EventSensorWatch Class Reference

Inheritance diagram for ev3::EventSensorWatch:



Public Member Functions

- **EventSensorWatch** (Sensor::SensorType type, SensorValue value)
- SensorValue **getValue** ()
- Sensor::SensorType **getType** ()


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/communication/Event.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/communication/Event.cpp

4.35 ev3dev::gyro_sensor Class Reference

Inheritance diagram for ev3dev::gyro_sensor:



Public Member Functions

- **gyro_sensor** (address_type address=INPUT_AUTO)
- int **angle** ()
- int **rate** ()

Static Public Attributes

- static const std::string **mode_gyro_ang** { "GYRO-ANG" }
- static const std::string **mode_gyro_rate** { "GYRO-RATE" }
- static const std::string **mode_gyro_fas** { "GYRO-FAS" }
- static const std::string **mode_gyro_g_a** { "GYRO-G&A" }
- static const std::string **mode_gyro_cal** { "GYRO-CAL" }


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.36 ev3dev::i2c_sensor Class Reference

Inheritance diagram for ev3dev::i2c_sensor:



Public Member Functions

- **i2c_sensor** (address_type address=INPUT_AUTO)
- std::string **fw_version** () const
- int **poll_ms** () const
- auto **set_poll_ms** (int v) -> decltype(*this)


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.37 ev3dev::infrared_sensor Class Reference

Inheritance diagram for ev3dev::infrared_sensor:



Public Member Functions

- **infrared_sensor** (address_type address=INPUT_AUTO)
- int **proximity** ()

Static Public Attributes

- static const std::string **mode_ir_prox** { "IR-PROX" }
- static const std::string **mode_ir_seek** { "IR-SEEK" }
- static const std::string **mode_ir_remote** { "IR-REMOTE" }
- static const std::string **mode_ir_rem_a** { "IR-REM-A" }
- static const std::string **mode_ir_cal** { "IR-CAL" }


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.38 ev3dev::large_motor Class Reference

Inheritance diagram for ev3dev::large_motor:



Public Member Functions

- **large_motor** (address_type address=OUTPUT_AUTO)

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.39 ev3dev::lcd Class Reference

Public Member Functions

- bool **available** () const
- uint32_t **resolution_x** () const
- uint32_t **resolution_y** () const
- uint32_t **bits_per_pixel** () const
- uint32_t **frame_buffer_size** () const
- uint32_t **line_length** () const
- unsigned char * **frame_buffer** ()
- void **fill** (unsigned char pixel)

Protected Member Functions


- void **init** ()
- void **deinit** ()

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.40 ev3dev::led Class Reference

Inheritance diagram for ev3dev::led:



Public Member Functions

- **led** (std::string name)
- int **max_brightness** () const
- int **brightness** () const
- auto **set_brightness** (int v) -> decltype(*this)
- mode_set **triggers** () const
- std::string **trigger** () const
- auto **set_trigger** (std::string v) -> decltype(*this)
- int **delay_on** () const
- auto **set_delay_on** (int v) -> decltype(*this)
- int **delay_off** () const
- auto **set_delay_off** (int v) -> decltype(*this)
- float **brightness_pct** () const
- auto **set_brightness_pct** (float v) -> decltype(*this)
- void **on** ()
- void **off** ()
- void **flash** (unsigned on_ms, unsigned off_ms)

Static Public Member Functions

- static void **set_color** (const std::vector< [led](#) * > &group, const std::vector< float > &color)
- static void **all_off** ()

Static Public Attributes

- static [led](#) **red_left** {"ev3:left:red:ev3dev"}
- static [led](#) **red_right** {"ev3:right:red:ev3dev"}
- static [led](#) **green_left** {"ev3:left:green:ev3dev"}
- static [led](#) **green_right** {"ev3:right:green:ev3dev"}
- static std::vector< [led](#) * > **left** { &led::red_left, &led::green_left }
- static std::vector< [led](#) * > **right** { &led::red_right, &led::green_right }
- static std::vector< float > **red** { static_cast<float>(1), static_cast<float>(0) }
- static std::vector< float > **green** { static_cast<float>(0), static_cast<float>(1) }
- static std::vector< float > **amber** { static_cast<float>(1), static_cast<float>(1) }
- static std::vector< float > **orange** { static_cast<float>(1), static_cast<float>(0.5) }
- static std::vector< float > **yellow** { static_cast<float>(0.5), static_cast<float>(1) }

Protected Attributes

- int **_max_brightness** = 0

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.41 ev3::LedControl Class Reference

Public Types

- enum **LedType** {
RED_L = 1, **RED_R** = 1 << 1, **GREEN_L** = 1 << 2, **GREEN_R** = 1 << 3,
RED_ALL = **RED_L** | **RED_R**, **GREEN_ALL** = **GREEN_L** | **GREEN_R**, **ALL** = **RED_ALL** | **GREEN_ALL** }
- enum **LedColors** { **RED**, **AMBER**, **YELLOW**, **GREEN** }

Public Member Functions

- void **on** (unsigned int leds=LedType::ALL, unsigned int brightness=MAX_BRIGHTNESS)
- void **onExclusive** (unsigned int leds=LedType::ALL, unsigned int brightness=MAX_BRIGHTNESS)
- void **off** (unsigned int leds=LedType::ALL)
- void **setColor** (LedColors color)
- void **reset** ()
- void **flash** (unsigned int leds, unsigned int msInterval, unsigned int repeat=1, unsigned int brightness↔
Red=MAX_BRIGHTNESS, unsigned int brightnessGreen=MAX_BRIGHTNESS)
- void **flashColor** (LedColors color, unsigned int msInterval, unsigned int repeat=1)
- void **endFlashing** ()

Static Public Attributes


- static const unsigned int **MAX_BRIGHTNESS** = 255

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/control/LedControl.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/control/LedControl.cpp

4.42 ev3dev::lego_port Class Reference

Inheritance diagram for ev3dev::lego_port:



Public Member Functions

- **lego_port** (address_type)
- std::string **driver_name** () const
- mode_set **modes** () const
- std::string **mode** () const
- auto **set_mode** (std::string v) -> decltype(*this)
- std::string **address** () const
- auto **set_set_device** (std::string v) -> decltype(*this)
- std::string **status** () const

Protected Member Functions

- bool **connect** (const std::map< std::string, std::set< std::string >> &) noexcept


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.43 ev3dev::light_sensor Class Reference

Inheritance diagram for ev3dev::light_sensor:



Public Member Functions

- **light_sensor** (address_type address=INPUT_AUTO)
- float **reflected_light_intensity** ()
- float **ambient_light_intensity** ()

Static Public Attributes

- static const std::string **mode_reflect** { "REFLECT" }
- static const std::string **mode_ambient** { "AMBIENT" }

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.44 ev3::Logger Class Reference

Public Types

- enum **LogLevel** {
 DEBUG = 1, **VERBOSE** = 1 << 1, **INFO** = 1 << 2, **WARNING** = 1 << 3,
 ERROR = 1 << 4 }
- enum **LogOutput** { **STD_OUT** = 1, **STD_ERR** = 1 << 1, **FILE** = 1 << 2 }

Public Member Functions

- void **log** (std::string message, LogLevel level, LogOutput output=STD_OUT)
- void **setLogLevel** (LogLevel level)
- void **setLogLevel** (std::string level)
- void **setLogOutput** (LogOutput output)

Static Public Member Functions

- static [Logger](#) * **getInstance** ()
- static void **destroy** ()

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/utils/Logger.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/utils/Logger.cpp

4.45 ev3::Master Class Reference

Public Types

- typedef std::map< unsigned int, [Agent](#) > **AgentMap**

Public Member Functions


- std::thread **createThread** ([Queue](#)< [Message](#) > *sendQueue, [Queue](#)< [Message](#) > *receiveQueue)
- void **run** ([Queue](#)< [Message](#) > *sendQueue, [Queue](#)< [Message](#) > *receiveQueue)
- void **send** ([Message](#) message, bool recordMessage=true)
- void **stop** ()

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/master/Master.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/master/Master.cpp

4.46 ev3dev::medium_motor Class Reference

Inheritance diagram for ev3dev::medium_motor:



Public Member Functions

- **medium_motor** (address_type address=OUTPUT_AUTO)

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.47 ev3::Message Class Reference

Public Types

- enum **MessageType** {
EMPTY, **ACK**, **NOT**, **AGENT**,
MASTER, **MASTER_OVER**, **PING**, **PONG**,
AGENT_OVER, **ABORT**, **BEHAVIOUR**, **START**,
RESUME, **PAUSE**, **ACTION_OK**, **ACTION_INTERR**,
SENSOR_VALUE, **MEASURE** }

Public Member Functions

- **Message** (unsigned int senderId, unsigned int receiverId, unsigned int messageId, MessageType type, StringVector parameters={})
- unsigned int **getSenderId** ()
- unsigned int **getReceiverId** ()
- unsigned int **getMessageId** ()
- MessageType **getType** ()
- StringVector **getParameters** ()
- void **setSenderId** (unsigned int id)
- void **setReceiverId** (unsigned int id)
- void **setMessageId** (unsigned int id)
- void **setType** (MessageType type)
- void **setParameters** (StringVector parameters)
- bool **empty** ()
- std::string **getString** ()
- void **reset** ()

Static Public Member Functions

- static std::string **encodeMessage** ([Message](#) &message)
- static [Message](#) **decodeMessage** (const std::string msg)

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/communication/Message.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/communication/Message.cpp

4.48 [ev3::Motor](#) Class Reference

Public Member Functions


- **Motor** ([ev3dev::motor](#) motor)
- [ev3dev::motor](#) **getMotor** ()

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/Motor.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/Motor.cpp

4.49 [ev3dev::motor](#) Class Reference

Inheritance diagram for [ev3dev::motor](#):



Public Types

- typedef device_type **motor_type**

Public Member Functions

- **motor** (address_type)
- **motor** (address_type, const motor_type &)
- auto **set_command** (std::string v) -> decltype(*this)
- mode_set **commands** () const
- int **count_per_rot** () const
- std::string **driver_name** () const
- int **duty_cycle** () const
- int **duty_cycle_sp** () const
- auto **set_duty_cycle_sp** (int v) -> decltype(*this)
- std::string **encoder_polarity** () const
- auto **set_encoder_polarity** (std::string v) -> decltype(*this)
- std::string **polarity** () const
- auto **set_polarity** (std::string v) -> decltype(*this)
- std::string **address** () const
- int **position** () const
- auto **set_position** (int v) -> decltype(*this)
- int **position_p** () const
- auto **set_position_p** (int v) -> decltype(*this)
- int **position_i** () const
- auto **set_position_i** (int v) -> decltype(*this)
- int **position_d** () const
- auto **set_position_d** (int v) -> decltype(*this)
- int **position_sp** () const
- auto **set_position_sp** (int v) -> decltype(*this)
- int **speed** () const
- int **speed_sp** () const
- auto **set_speed_sp** (int v) -> decltype(*this)
- int **ramp_up_sp** () const
- auto **set_ramp_up_sp** (int v) -> decltype(*this)
- int **ramp_down_sp** () const
- auto **set_ramp_down_sp** (int v) -> decltype(*this)
- std::string **speed_regulation_enabled** () const
- auto **set_speed_regulation_enabled** (std::string v) -> decltype(*this)
- int **speed_regulation_p** () const
- auto **set_speed_regulation_p** (int v) -> decltype(*this)
- int **speed_regulation_i** () const
- auto **set_speed_regulation_i** (int v) -> decltype(*this)
- int **speed_regulation_d** () const
- auto **set_speed_regulation_d** (int v) -> decltype(*this)
- mode_set **state** () const
- std::string **stop_command** () const
- auto **set_stop_command** (std::string v) -> decltype(*this)
- mode_set **stop_commands** () const
- int **time_sp** () const
- auto **set_time_sp** (int v) -> decltype(*this)
- void **run_forever** ()
- void **run_to_abs_pos** ()
- void **run_to_rel_pos** ()
- void **run_timed** ()
- void **run_direct** ()
- void **stop** ()
- void **reset** ()
- motor_type **type_name** ()

Static Public Attributes

- static const motor_type **motor_large** { "lego-ev3-l-motor" }
- static const motor_type **motor_medium** { "lego-ev3-m-motor" }
- static const std::string **command_run_forever** { "run-forever" }
- static const std::string **command_run_to_abs_pos** { "run-to-abs-pos" }
- static const std::string **command_run_to_rel_pos** { "run-to-rel-pos" }
- static const std::string **command_run_timed** { "run-timed" }
- static const std::string **command_run_direct** { "run-direct" }
- static const std::string **command_stop** { "stop" }
- static const std::string **command_reset** { "reset" }
- static const std::string **encoder_polarity_normal** { "normal" }
- static const std::string **encoder_polarity_inversed** { "inversed" }
- static const std::string **polarity_normal** { "normal" }
- static const std::string **polarity_inversed** { "inversed" }
- static const std::string **speed_regulation_on** { "on" }
- static const std::string **speed_regulation_off** { "off" }
- static const std::string **stop_command_coast** { "coast" }
- static const std::string **stop_command_brake** { "brake" }
- static const std::string **stop_command_hold** { "hold" }

Protected Member Functions

- bool **connect** (const std::map< std::string, std::set< std::string >> &) noexcept

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.50 ev3::CommUtils::NetworkNode Struct Reference

Public Attributes


- unsigned int **port**
- std::string **ipAddress**

The documentation for this struct was generated from the following file:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/communication/CommUtils.h

4.51 ev3dev::power_supply Class Reference

Inheritance diagram for ev3dev::power_supply:



Public Member Functions

- **power_supply** (std::string name)
- int **measured_current** () const
- int **measured_voltage** () const
- int **max_voltage** () const
- int **min_voltage** () const
- std::string **technology** () const
- std::string **type** () const
- float **measured_amps** () const
- float **measured_volts** () const

Static Public Attributes

- static **power_supply** **battery** { "" }

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.52 ev3::Queue< T > Class Template Reference

Public Member Functions

- void **push** (T message)
- T **pop** ()
- bool **empty** ()

The documentation for this class was generated from the following file:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/Utils/Queue.h

4.53 ev3dev::remote_control Class Reference

Public Types

- enum **buttons** {
red_up = (1 << 0), **red_down** = (1 << 1), **blue_up** = (1 << 2), **blue_down** = (1 << 3),
beacon = (1 << 4) }

Public Member Functions

- remote_control** (unsigned channel=1)
- remote_control** ([infrared_sensor](#) &, unsigned channel=1)
- bool **connected** () const
- unsigned **channel** () const
- bool **process** ()

Public Attributes

- std::function< void(bool)> **on_red_up**
- std::function< void(bool)> **on_red_down**
- std::function< void(bool)> **on_blue_up**
- std::function< void(bool)> **on_blue_down**
- std::function< void(bool)> **on_beacon**
- std::function< void(int)> **on_state_change**

Protected Member Functions

- virtual void **on_value_changed** (int value)

Protected Attributes


- [infrared_sensor](#) * **_sensor** = nullptr
- bool **_owns_sensor** = false
- unsigned **_channel** = 0
- int **_value** = 0
- int **_state** = 0

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.54 ev3::Robot Class Reference

Inheritance diagram for ev3::Robot:



Public Types

- typedef std::vector< [Action::ActionType](#) > [AvailableActions](#)
Type for specifying all available actions for given [Robot](#) model.

Public Member Functions

- **Robot** (Devices::RequiredDevices devices, [AvailableActions](#) actions)
- std::thread **createThread** ([Queue< Message > *sendQueue](#), [Queue< Message > *receiveQueue](#))
- virtual void **run** ([Queue< Message > *sendQueue](#), [Queue< Message > *receiveQueue](#))
- void **stop** ()
- void **send** ([Message](#) message)
- virtual std::string **getString** ()

Protected Member Functions

- virtual [SharedPtrBehaviour](#) **generateBehaviour** ([Behaviour::BehaviourType](#) type, StringVector parameters)

Protected Attributes


- unsigned int **_id** = 0
- unsigned int **_commId** = 0
- float **_pulsePerUnitRatio** = 1.f
- Devices::RequiredDevices **_requiredDevices**
- [AvailableActions](#) **_availableActions**
- [Queue< Message > * _sendQueue](#)
- [Queue< Message > * _receiveQueue](#)
- [LedControl](#) **_ledControl**
- [RobotState](#) * **_state** = new [RobotStateIdle](#)(&_ledControl)

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/Robot.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/Robot.cpp

4.55 ev3::RobotModelA Class Reference

Inheritance diagram for ev3::RobotModelA:



Public Member Functions

- virtual std::string **getString** () override


Additional Inherited Members

The documentation for this class was generated from the following files:

- `/home/panda/Dokumenty/Repos/Ev3Dev/include/robot/RobotModelA.h`
- `/home/panda/Dokumenty/Repos/Ev3Dev/src/robot/RobotModelA.cpp`

4.56 ev3::RobotState Class Reference

Inheritance diagram for `ev3::RobotState`:



Public Types

- enum **States** {
 IDLE, **ACTIVE**, **WORKING**, **PAUSED**,
 PANIC }
- typedef std::map< Message::MessageType, States > **ChangeMap**

Public Member Functions

- **RobotState** (ChangeMap changes, [LedControl](#) *led)
- virtual [RobotState](#) * **process** ([Message](#) msg)
- Message::MessageType **getPendingMessage** ()
- void **updateTimer** ()
- bool **isPendingEnabled** ()
- void **setBehaviour** ([SharedPtrBehaviour](#) behaviour)
- [SharedPtrBehaviour](#) **getBehaviour** ()

Static Public Attributes

- static const float **MASTER_TIMEOUT** = 10.f * 1000
- static const float **MASTER_PING_TIME** = 3.f * 1000

Protected Member Functions

- [RobotState](#) * **switchState** (Message::MessageType type)
- [RobotState](#) * **changeState** (States state)

Protected Attributes


- [SharedPtrBehaviour](#) **_currentBehaviour**
- States **_state**
- ChangeMap **_changes**
- [LedControl](#) * **_led**
- Message::MessageType **_pendingMessage** = Message::EMPTY
- float **_pendingTimeout** = 0.f
- HighResClock::time_point **_masterTimeout** = HighResClock::now()
- HighResClock::time_point **_messageDelay** = HighResClock::now()

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/RobotState.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/RobotState.cpp

4.57 ev3::RobotStateActive Class Reference

Inheritance diagram for ev3::RobotStateActive:



Public Member Functions

- **RobotStateActive** ([LedControl](#) *led)
- [RobotState](#) * **process** ([Message](#) msg)


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/RobotState.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/RobotState.cpp

4.58 ev3::RobotStateIdle Class Reference

Inheritance diagram for ev3::RobotStateIdle:



Public Member Functions

- **RobotStateIdle** ([LedControl](#) *led)
- **RobotState** * **process** ([Message](#) msg)


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/RobotState.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/RobotState.cpp

4.59 ev3::RobotStatePanic Class Reference

Inheritance diagram for ev3::RobotStatePanic:



Public Member Functions

- **RobotStatePanic** ([LedControl](#) *led)
- **RobotState** * **process** ([Message](#) msg)


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/RobotState.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/RobotState.cpp

4.60 ev3::RobotStatePaused Class Reference

Inheritance diagram for ev3::RobotStatePaused:



Public Member Functions

- **RobotStatePaused** ([LedControl](#) *led)
- [RobotState](#) * **process** ([Message](#) msg)


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/RobotState.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/RobotState.cpp

4.61 ev3::RobotStateWorking Class Reference

Inheritance diagram for ev3::RobotStateWorking:



Public Member Functions

- **RobotStateWorking** ([LedControl](#) *led)
- [RobotState](#) * **process** ([Message](#) msg)


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/RobotState.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/RobotState.cpp

4.62 ev3dev::sensor Class Reference

Inheritance diagram for ev3dev::sensor:



Public Types

- typedef device_type **sensor_type**

Public Member Functions

- **sensor** (address_type)
- **sensor** (address_type, const std::set< sensor_type > &)
- int **value** (unsigned index=0) const
- float **float_value** (unsigned index=0) const
- std::string **type_name** () const
- std::string **bin_data_format** () const
- const std::vector< char > & **bin_data** () const
- template<class T >
void **bin_data** (T *buf) const
- auto **set_command** (std::string v) -> decltype(*this)
- mode_set **commands** () const
- int **decimals** () const
- std::string **driver_name** () const
- std::string **mode** () const
- auto **set_mode** (std::string v) -> decltype(*this)
- mode_set **modes** () const
- int **num_values** () const
- std::string **address** () const
- std::string **units** () const

Static Public Attributes

- static const sensor_type **ev3_touch** { "lego-ev3-touch" }
- static const sensor_type **ev3_color** { "lego-ev3-color" }
- static const sensor_type **ev3_ultrasonic** { "lego-ev3-us" }
- static const sensor_type **ev3_gyro** { "lego-ev3-gyro" }
- static const sensor_type **ev3_infrared** { "lego-ev3-ir" }
- static const sensor_type **nxt_touch** { "lego-nxt-touch" }
- static const sensor_type **nxt_light** { "lego-nxt-light" }
- static const sensor_type **nxt_sound** { "lego-nxt-sound" }
- static const sensor_type **nxt_ultrasonic** { "lego-nxt-us" }
- static const sensor_type **nxt_i2c_sensor** { "nxt-i2c-sensor" }
- static const sensor_type **nxt_analog** { "nxt-analog" }

Protected Member Functions

- bool **connect** (const std::map< std::string, std::set< std::string >> &) noexcept

Protected Attributes

- std::vector< char > **_bin_data**

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.63 ev3::Sensor Class Reference

Public Types

- enum **SensorType** {
 TOUCH, **COLOR**, **ULTRASONIC**, **GYRO**,
 INFRARED, **SOUND**, **LIGHT** }

Public Member Functions

- **Sensor** ([ev3dev::sensor](#) sensor, SensorType type)
- [ev3dev::sensor](#) **getSensor** ()
- int **getValue** (unsigned int n)
- float **getValueF** (unsigned int n)
- int **getDecimals** ()
- unsigned int **getNumValues** ()
- SensorType **getType** ()

Static Public Member Functions


- static StringVector **prepareMessage** (SensorValue value, SensorType type)

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/robot/Sensor.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/robot/Sensor.cpp

4.64 ev3dev::servo_motor Class Reference

Inheritance diagram for ev3dev::servo_motor:



Public Member Functions

- **servo_motor** (address_type address=OUTPUT_AUTO)
- auto **set_command** (std::string v) -> decltype(*this)
- std::string **driver_name** () const
- int **max_pulse_sp** () const
- auto **set_max_pulse_sp** (int v) -> decltype(*this)
- int **mid_pulse_sp** () const
- auto **set_mid_pulse_sp** (int v) -> decltype(*this)
- int **min_pulse_sp** () const
- auto **set_min_pulse_sp** (int v) -> decltype(*this)
- std::string **polarity** () const
- auto **set_polarity** (std::string v) -> decltype(*this)
- std::string **address** () const
- int **position_sp** () const
- auto **set_position_sp** (int v) -> decltype(*this)
- int **rate_sp** () const
- auto **set_rate_sp** (int v) -> decltype(*this)
- mode_set **state** () const
- void **run** ()
- void **float_** ()

Static Public Attributes

- static const std::string **command_run** { "run" }
- static const std::string **command_float** { "float" }
- static const std::string **polarity_normal** { "normal" }
- static const std::string **polarity_inversed** { "inversed" }

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.65 ev3::SignalHandler Class Reference

Static Public Member Functions

- static void **HandleSignal** (int signum)

Static Public Attributes

- static [Robot](#) * **robot** = nullptr
- static [Master](#) * **master** = nullptr

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/Utils/SignalHandler.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/Utils/SignalHandler.cpp

4.66 ev3dev::sound Class Reference

Static Public Member Functions


- static void **beep** (const std::string &args="", bool bSynchronous=false)
- static void **tone** (float frequency, float ms, bool bSynchronous=false)
- static void **tone** (const std::vector< std::vector< float > > &sequence, bool bSynchronous=false)
- static void **play** (const std::string &soundfile, bool bSynchronous=false)
- static void **speak** (const std::string &text, bool bSynchronous=false)

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.67 ev3dev::sound_sensor Class Reference

Inheritance diagram for ev3dev::sound_sensor:



Public Member Functions

- **sound_sensor** (address_type address=INPUT_AUTO)
- float **sound_pressure** ()
- float **sound_pressure_low** ()

Static Public Attributes

- static const std::string **mode_db** { "DB" }
- static const std::string **mode_dba** { "DBA" }


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.68 ev3dev::touch_sensor Class Reference

Inheritance diagram for ev3dev::touch_sensor:



Public Member Functions

- **touch_sensor** (address_type address=INPUT_AUTO)
- bool **is_pressed** ()

Static Public Attributes

- static const std::string **mode_touch** { "TOUCH" }


Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

4.69 ev3dev::ultrasonic_sensor Class Reference

Inheritance diagram for ev3dev::ultrasonic_sensor:



Public Member Functions

- **ultrasonic_sensor** (address_type address=INPUT_AUTO)
- float **distance_centimeters** ()
- float **distance_inches** ()
- bool **other_sensor_present** ()

Static Public Attributes

- static const std::string **mode_us_dist_cm** { "US-DIST-CM" }
- static const std::string **mode_us_dist_in** { "US-DIST-IN" }
- static const std::string **mode_us_listen** { "US-LISTEN" }
- static const std::string **mode_us_si_cm** { "US-SI-CM" }
- static const std::string **mode_us_si_in** { "US-SI-IN" }

Additional Inherited Members

The documentation for this class was generated from the following files:

- /home/panda/Dokumenty/Repos/Ev3Dev/include/ev3dev/ev3dev.h
- /home/panda/Dokumenty/Repos/Ev3Dev/src/ev3dev/ev3dev.cpp

Chapter 5

File Documentation

5.1 /home/panda/Dokumenty/Repos/Ev3Dev/include/action/Action.h File Reference

Contains all Action classes.

```
#include "CommandMotor.h"
#include <memory>
```

Classes

- class [ev3::Action](#)
Base class for all [Action](#) controlling classes.
- class [ev3::ActionRepeat](#)
Stores many [Actions](#) in a vector and executes them in loop.
- class [ev3::ActionDriveDistance](#)
Implements [Robot](#) simple task to drive straight for a given distance.
- class [ev3::ActionRotate](#)
Implements [Robot](#) simple task to rotate a given angle, while not driving.
- class [ev3::ActionRotateRandDirection](#)
Implements [Robot](#) simple task to rotate a random angle.
- class [ev3::ActionStop](#)
Implements [Robot](#) simple task to stop all active motors.
- class [ev3::ActionDriveForever](#)
Implements [Robot](#) simple task to drive straight forever.

Typedefs

- typedef std::shared_ptr< Action > [ev3::SharedPtrAction](#)
Type for [Action](#) [shared_ptr](#).
- typedef std::vector< SharedPtrAction > [ev3::StoredActions](#)
Type for storing many [Actions](#) in one container.
- typedef std::shared_ptr< Command > [ev3::SharedPtrCommand](#)
Type for [Command](#) [shared_ptr](#).
- typedef std::vector< SharedPtrCommand > [ev3::CommandsVector](#)
Type for containing associated [Command](#) pointers.

5.1.1 Detailed Description

Contains all Action classes.

5.1.2 Typedef Documentation

5.1.2.1 `typedef std::vector<SharedPtrAction> ev3::StoredActions`

Type for storing many Actions in one container.

See also

[ActionRepeat](#)

5.2 `/home/panda/Dokumenty/Repos/Ev3Dev/include/action/Behaviour.h` File Reference

Contains all Behaviour classes.

```
#include "Action.h"
#include "Utils.h"
#include "Sensor.h"
#include "Event.h"
#include "BehaviourState.h"
#include <unistd.h>
#include <string>
```

Classes

- class [ev3::Behaviour](#)
Base class for all defined behaviours.
- class [ev3::BehaviourDriveOnSquare](#)
- class [ev3::BehaviourExploreRandom](#)

Typedefs

- typedef `std::shared_ptr< Behaviour >` [ev3::SharedPtrBehaviour](#)
Type for [Behaviour](#) `shared_ptr`.
- typedef `std::vector< BehaviourState >` [ev3::BehaviourStates](#)
Type for storing [Behaviour](#) states in one container.
- typedef `std::vector< Sensor::SensorType >` [ev3::Measurements](#)
Type for storing sensors' desired measurements in one container.

5.2.1 Detailed Description

Contains all Behaviour classes.

5.3 /home/panda/Dokumenty/Repos/Ev3Dev/include/action/BehaviourState.h File Reference

Contains BehaviourState class.

```
#include "Action.h"  
#include "Event.h"
```

Classes

- class [ev3::BehaviourState](#)

Typedefs

- typedef std::map< Event::EventType, unsigned int > **ev3::ReactionsTransitions**

5.3.1 Detailed Description

Contains BehaviourState class.

Index

/home/panda/Dokumenty/Repos/Ev3Dev/include/action/↔
Action.h, 73

/home/panda/Dokumenty/Repos/Ev3Dev/include/action/↔
Behaviour.h, 74

/home/panda/Dokumenty/Repos/Ev3Dev/include/action/↔
BehaviourState.h, 75

_endCondition
ev3::Action, 11

Action
ev3::Action, 9

Action.h
StoredActions, 74

ActionDriveDistance
ev3::ActionDriveDistance, 12

ActionDriveForever
ev3::ActionDriveForever, 14

ActionRepeat
ev3::ActionRepeat, 16

ActionRotate
ev3::ActionRotate, 17

ActionRotateRandDirection
ev3::ActionRotateRandDirection, 19

ActionStop
ev3::ActionStop, 21

ActionType
ev3::Action, 9

BRAKE
ev3::CommandMotorSetStopMode, 39

Behaviour
ev3::Behaviour, 24

BehaviourType
ev3::Behaviour, 24

COAST
ev3::CommandMotorSetStopMode, 39

CUSTOM
ev3::Behaviour, 24

CommandMotor
ev3::CommandMotor, 33

CommandMotorReset
ev3::CommandMotorReset, 34

CommandMotorRunForever
ev3::CommandMotorRunForever, 35

CommandMotorSetSpeed
ev3::CommandMotorSetSpeed, 36

CommandMotorSetSpeedRegEnabled
ev3::CommandMotorSetSpeedRegEnabled, 37

CommandMotorSetStopMode
ev3::CommandMotorSetStopMode, 39

CommandMotorStop
ev3::CommandMotorStop, 40

CommandSensor
ev3::CommandSensor, 41

DRIVE_DISTANCE
ev3::Action, 9

DRIVE_FOREVER
ev3::Action, 9

DRIVE_ON_SQUARE
ev3::Behaviour, 24

EXPLORE_RANDOM
ev3::Behaviour, 24

ev3::Action, 7
_endCondition, 11
Action, 9
ActionType, 9
DRIVE_DISTANCE, 9
DRIVE_FOREVER, 9
getActionPrototype, 10
getString, 10
getType, 10
isExecuted, 10
isFinished, 10
NOP, 9
REPEAT, 9
ROTATE_RANDOM_DIR, 9
ROTATE, 9
STOP, 9
setCommands, 10
setEndCondition, 11
ev3::ActionDriveDistance, 11
ActionDriveDistance, 12
getActionPrototype, 12
getDistance, 13
getString, 13
ev3::ActionDriveForever, 13
ActionDriveForever, 14
getActionPrototype, 14
getString, 15
isForward, 15
ev3::ActionRepeat, 15
ActionRepeat, 16
getString, 16
ev3::ActionRotate, 16
ActionRotate, 17
getActionPrototype, 18
getRotation, 18

- getString, 18
- ev3::ActionRotateRandDirection, 18
 - ActionRotateRandDirection, 19
 - execute, 19
 - getActionPrototype, 20
 - getString, 20
- ev3::ActionStop, 20
 - ActionStop, 21
 - getActionPrototype, 21
 - getString, 21
- ev3::Agent, 22
- ev3::Behaviour, 22
 - Behaviour, 24
 - BehaviourType, 24
 - CUSTOM, 24
 - DRIVE_ON_SQUARE, 24
 - EXPLORE_RANDOM, 24
 - getPrototype, 24
 - getString, 25
 - react, 25
 - setMeasurements, 25
 - setReactionStates, 25
 - setStates, 25
 - setStopState, 26
- ev3::BehaviourDriveOnSquare, 26
 - getPrototype, 26
 - getString, 26
- ev3::BehaviourExploreRandom, 27
 - getPrototype, 27
 - getString, 27
- ev3::BehaviourState, 28
- ev3::CircularBuffer< T >, 29
- ev3::ColorUtils, 30
- ev3::CommUtils, 42
- ev3::CommUtils::NetworkNode, 58
- ev3::Command, 31
 - getString, 32
- ev3::CommandMotor, 32
 - CommandMotor, 33
 - getMotor, 33
- ev3::CommandMotorReset, 34
 - CommandMotorReset, 34
- ev3::CommandMotorRunForever, 35
 - CommandMotorRunForever, 35
- ev3::CommandMotorSetSpeed, 36
 - CommandMotorSetSpeed, 36
- ev3::CommandMotorSetSpeedRegEnabled, 37
 - CommandMotorSetSpeedRegEnabled, 37
- ev3::CommandMotorSetStopMode, 38
 - BRAKE, 39
 - COAST, 39
 - CommandMotorSetStopMode, 39
 - HOLD, 39
 - StopMode, 39
- ev3::CommandMotorStop, 39
 - CommandMotorStop, 40
- ev3::CommandSensor, 40
 - CommandSensor, 41
- getSensor, 41
- ev3::Communication, 41
- ev3::Devices, 44
- ev3::Event, 45
- ev3::EventAction, 46
- ev3::EventQueue, 46
- ev3::EventSensorWatch, 47
- ev3::LedControl, 52
- ev3::Logger, 54
- ev3::Master, 54
- ev3::Message, 55
- ev3::Motor, 56
- ev3::Queue< T >, 59
- ev3::Robot, 60
- ev3::RobotModelA, 61
- ev3::RobotState, 62
- ev3::RobotStateActive, 63
- ev3::RobotStateIdle, 63
- ev3::RobotStatePanic, 64
- ev3::RobotStatePaused, 64
- ev3::RobotStateWorking, 65
- ev3::Sensor, 67
- ev3::SignalHandler, 69
- ev3dev::button, 28
- ev3dev::color_sensor, 29
- ev3dev::dc_motor, 42
- ev3dev::device, 43
- ev3dev::gyro_sensor, 47
- ev3dev::i2c_sensor, 48
- ev3dev::infrared_sensor, 49
- ev3dev::large_motor, 49
- ev3dev::lcd, 50
- ev3dev::led, 50
- ev3dev::lego_port, 52
- ev3dev::light_sensor, 53
- ev3dev::medium_motor, 55
- ev3dev::motor, 56
- ev3dev::power_supply, 59
- ev3dev::remote_control, 60
- ev3dev::sensor, 66
- ev3dev::servo_motor, 68
- ev3dev::sound, 69
- ev3dev::sound_sensor, 69
- ev3dev::touch_sensor, 70
- ev3dev::ultrasonic_sensor, 71
- execute
 - ev3::ActionRotateRandDirection, 19
- getActionPrototype
 - ev3::Action, 10
 - ev3::ActionDriveDistance, 12
 - ev3::ActionDriveForever, 14
 - ev3::ActionRotate, 18
 - ev3::ActionRotateRandDirection, 20
 - ev3::ActionStop, 21
- getDistance
 - ev3::ActionDriveDistance, 13
- getMotor
 - ev3::CommandMotor, 33

getPrototype
 ev3::Behaviour, [24](#)
 ev3::BehaviourDriveOnSquare, [26](#)
 ev3::BehaviourExploreRandom, [27](#)
getRotation
 ev3::ActionRotate, [18](#)
getSensor
 ev3::CommandSensor, [41](#)
getString
 ev3::Action, [10](#)
 ev3::ActionDriveDistance, [13](#)
 ev3::ActionDriveForever, [15](#)
 ev3::ActionRepeat, [16](#)
 ev3::ActionRotate, [18](#)
 ev3::ActionRotateRandDirection, [20](#)
 ev3::ActionStop, [21](#)
 ev3::Behaviour, [25](#)
 ev3::BehaviourDriveOnSquare, [26](#)
 ev3::BehaviourExploreRandom, [27](#)
 ev3::Command, [32](#)
getType
 ev3::Action, [10](#)

HOLD
 ev3::CommandMotorSetStopMode, [39](#)

isExecuted
 ev3::Action, [10](#)
isFinished
 ev3::Action, [10](#)
isForward
 ev3::ActionDriveForever, [15](#)

NOP
 ev3::Action, [9](#)

REPEAT
 ev3::Action, [9](#)
ROTATE_RANDOM_DIR
 ev3::Action, [9](#)
ROTATE
 ev3::Action, [9](#)
react
 ev3::Behaviour, [25](#)

STOP
 ev3::Action, [9](#)
setCommands
 ev3::Action, [10](#)
setEndCondition
 ev3::Action, [11](#)
setMeasurements
 ev3::Behaviour, [25](#)
setReactionStates
 ev3::Behaviour, [25](#)
setStates
 ev3::Behaviour, [25](#)
setStopState
 ev3::Behaviour, [26](#)

StopMode
 ev3::CommandMotorSetStopMode, [39](#)
StoredActions
 Action.h, [74](#)