

INSTRUCTIONS

Instructions for Word Picker

Welcome to word picker!

You can find words by sound or spelling pattern. To do it by sound, find the sound you want that is bolded in the example section of the table. Then find the corresponding phoneme and type it in the type sound here... input field. If you want to find words that have a sound or another sound, separate them with a comma.

If you want to find words using a spelling pattern, type in a spelling pattern. To find words that have a consonant, type in a capital C. For vowels, type a consonant V. If you only type in a capital C, it won't show any results because there are no words that are just a consonant and nothing else. To find words that contain a consonant (there are many), you need to type a dash in the end and the beginning of the C. The one at the end means that it should include results that start with a consonant. The one at the start shows that it should also include words that end with a consonant. But if you want to find words that shows a spelling pattern *and* another spelling pattern, separate them with a comma. A lowercase letter just means a additional letter that you typed. You can also double something, like a consonant. This will make the second one the same letter as the first. To do that, add a number after the thing you want to double, so the C for the consonant becomes C2. The number that you type in is the number of times it gets repeated. This is useful when it goes right after a C or V. To connect these, just type the next one after the one before it.

To find words that contain a spelling pattern and also contains a sound, enter both the sound and spelling pattern.

Instructions for sentence picker

Welcome to sentence picker! Type any word to find example sentences.

Word Picker API

If you want to request words or sentences with some criteria without needing to use the webpage, you can use our API. Send a get request to `wordpicker-eb.eba-zkdtc4h6.us-west-2.elasticbeanstalk.com` then add `/api/words` to the url for finding words and `/api/sentences` for finding sentences. For words, you can add `&pattern=` then the spelling pattern for the spelling pattern, `&phone=` then the sound for the sound, and `&filter=` then the filter for the filter.

User Interface (UI) instructions

The loading wheel

The loading wheel shows you that Word Picker is loading. It has a green background and has rounded corners. If the loading wheel doesn't hide for more than 10 seconds, it might happen because of these reasons:

- Your browser is just slow. Try updating your browser to the latest version.
- Your browser doesn't support something that is used by Word Picker. Make sure Javascript is enabled on your browser. It provides functionality to Word Picker.
- There is a problem in Word Picker. If it causes the loading wheel to spin continuously, the problem should be solved in a day or in less time than that.

How to navigate

Use the tabs at the left bar to navigate. If you are on a mobile device, the tabs are in the bottom. Because things might look weird on a mobile device, using Word Picker on a computer or desktop is recommended. You can also go switch tabs by pressing the up and down arrow keys.

The three dots in the heading

The three dots in the heading shows a menu for more actions like opening settings, viewing the word list, translating the page and more. Keep in mind that the translation uses Google Translate, which might not translate all of the content perfectly.

Settings

You can change Word Picker's behavior using Settings. To access it, press the three dots at the top and select settings. You can use it to control whether there is a random background every day instead of every time the page loads. You can also use it to make the result text italic and control the result container width. Change the result container

width when the words bump into each other. To save and apply the settings, press save. If you want to just close the settings without saving, press cancel. The settings should be able to save on browsers that support [Local Storage](#). If your browser does not support local storage, then a red text saying that your browser does not support it will show. If it shows, update your browser or switch to another one.

More three dots options

There are more options in the three dots dropdown menu. The first one is the reload option. Unlike the usual reload button in your browser, this reload button should retrieve a new copy of the page and load it. The button is useful when you want to make sure that the page is updated. Another button is the see word list button. This button will pop up a list of all the words that are used for finding words. There is also a button that toggles dark mode. Dark mode is a dark theme that makes things darker. By default, Word Picker will make the theme match the configured theme in the system. You can override this by pressing the dark mode button. It will say light mode if you pressed dark mode. Press the same button to go back to light mode. The button that opens settings is also here. Read the settings section for how to use it and what controls there are. Lastly, you can change the language by selecting a language in the dropdown. You will need to scroll down to see more controls.