

Mode Line Control

Description	Keystroke	Function	Notes / Example description
Emacs Mode Line See: 🔗 Customize	An early version of a page that will describe tools to manage the mode line. Currently PEL does not provide much support for controlling Emacs mode line. It provides the following: <ul style="list-style-type: none"> The pel-pkg-for-modeline customization group that contains the user-options used to activate mode line related packages: <ul style="list-style-type: none"> The delight external package 📦 PEL activates it when the pel-use-delight user-option is turned on (set to t). <ul style="list-style-type: none"> Access this customization group with <f11> M-1 <f2>. When delight is used, PEL activates short lighters for some minor-modes. The following commands can be used to provides the activation of extra information shown on the mode line.		
Open this PDF file. See also: 🔗 Help/Info	<f11> M-1 <f1>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the 🔗 Mode Line local PDF. If the prefix argument (like C-u or M--) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
🔗 Customize PEL mode line support	<f11> M-1 <f2>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL mode line support <ul style="list-style-type: none"> If OTHER-WINDOW is non-nil (use C-u), display in another window.
🔗 Customize Emacs mode line	<f11> M-1 <f3>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs mode line support: mode-line <ul style="list-style-type: none"> If OTHER-WINDOW is non-nil (use C-u), display in another window.
Toggle which-function-mode to display name of current function at point See also: 🔗 Help/Info	<ul style="list-style-type: none"> <f11> ? f <f11> M-1 f 	(which-function-mode &optional ARG)	Toggle mode line display of current function (Which Function mode). <ul style="list-style-type: none"> With a prefix argument ARG, enable Which Function mode if ARG is positive, and disable it otherwise. The which-function-mode is a global minor mode. When enabled, the current function name is continuously displayed in the mode line, in specific major modes where the concept of a <i>current function</i> makes sense. 👁️ Identify the major modes where you want this activated in the which-function-mode user-option with M-x customize-option which-function-mode . <ul style="list-style-type: none"> With PEL you can use: <ul style="list-style-type: none"> <f11> ? <f3> to access the which-func customization group. Note that it will provide access to the customization group even when the feature has not yet been loaded. <f11> <f2> o which-function-mode RET to access the user-option directly.
Toggle display of ace-window number on window mode line See also: 🔗 Windows	<ul style="list-style-type: none"> <f11> w # <f11> M-1 # 	(ace-window-display-mode &optional ARG)	Toggle the ace-window-display-mode, a minor mode that displays the ace window number of each window inside the left hand side of its mode line. 📦 Requires the ace-window external package. 📦 PEL activates it when the pel-use-ace-window user-option is turned on. Use <f11> w <f2> to access the customization group where you can turn it on.