



# Dockerfile Reference

(c) 2021 Lino Figueroa ([lino.figueroa@softwareone.com](mailto:lino.figueroa@softwareone.com))

.dockerignore

Instructions

FROM

LABEL

RUN

WORKDIR

ENV

ARG

COPY

ADD

EXPOSE

ENTRYPOINT

CMD

## .dockerignore

Patterns for files and folders to ignore when using COPY or ADD operations in the dockerfile.

## Instructions

### FROM

Base image. It's the first line of file.

```
FROM python:3.7-alpine
```

### LABEL

Adds metadata to images.

```
LABEL "com.example.vendor"="ACME Incorporated"
LABEL com.example.label-with-value="foo"
LABEL version="1.0"
LABEL description="This text illustrates \
that label-values can span multiple lines."
```

**MAINTAINER** is deprecated. Use **LABEL** instead.

```
LABEL maintainer= "email@mail.com"
```

## RUN

Executes a command inside the container.

```
RUN apk add --no-cache gcc musl-dev linux-headers
```

## WORKDIR

Set the working directory inside the container for any **RUN**, **CMD**, **ENTRYPOINT**, **COPY**, and **ADD** instructions that follow it in the Dockerfile. It will be created if does not exist.

If a relative path is provided, it will be relative to the path of the previous **WORKDIR** instruction.

```
WORKDIR /path/to/workdir
```

## ENV

```
ENV <key>=<value>
```

Sets the variable "key" to the value "value". Will be overwritten when using the "-e" docker parameter.

## ARG

Defines a variable that can be set when building the image.

```
ARG version
```

A default value can be set

```
ARG version=1.0.0
```

## COPY

Copy files from a local filesystem to the image . It supports wildcards (? \* ).

```
ADD /my-folder/* /application/
```

```
ADD . .
```

The later copies from the current folder in the local filesystem to the current WORKDIR in the image.

## ADD

Copy files from a local filesystem to the image. It supports wildcards (? \* ). The difference with COPY is that it uncompress tar.gz files and can be used to copy from external URLs.

```
COPY /my-folder/* /application/
```

```
COPY my_file.tgz .
```

The later copies the file from the current folder in the local filesystem to the current WORKDIR in the image and uncompress the file.

## EXPOSE

The container will listen in the given port and protocol.

```
EXPOSE port
```

```
EXPOSE port/protocol
```

## ENTRYPOINT

Defines a program to be executed when the container start and its parameters.

Can be overridden with the docker `--entrypoint` parameter.

Exec form (preferred)

```
ENTRYPOINT ["executable", "param1", "param2"]
```

Shell form:

```
ENTRYPOINT command param1 param2
```

# CMD

Defines default commands and/or parameters for a container. If a dockerfile has multiple CMDs will only execute the last one.

Exec form: (preferred)

```
CMD ["executable","param1","param2"]
```

Shell form:

```
CMD command param1 param2
```

Can be used to pass default parameters to ENTRYPOINT.

```
CMD ["param1","param2"]
```

(c) 2021 Lino Figueroa ([lino.figueroa@softwareone.com](mailto:lino.figueroa@softwareone.com))