

Worked on some cli command:

```
mir-connection-04bmh6d3phq.messaging.solace.cloud - PuTTY
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue)
# exit
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool)# crea
te queue-template queuetp01
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# show queue-template *
Message VPN Queue Template Name Filter
-----
message-vpn01 queuetp01
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# access-type non-exclusive
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# max-spool-usage 50
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# permission all consume
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# permission all read-only
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# name-filter topic/name/*
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# durability-override non-durable
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# no consumer-ack-propagation
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# consumer-ack-propagation
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# access-type exclusive
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# durability-override durable

Invalid command input
  durability-override durable
                ^
-> invalid parameter
Expected one of the following:
  none          - The durability of the endpoint will be as requested on
                  create.
  non-durable   - The durability of the created queue will be non-durable,
                  regardless of what was requested.

developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)# durability-override none
developer-production-vhexguja2ku-solace-primary-0(configure/message-spool/queue-
template)#
```

The screenshot displays the Solace CLI interface and the Solace Cloud UI. The CLI shows the configuration of a queue template named 'queuetp01' with various settings like access-type, max-spool-usage, permission, name-filter, and durability-override. The Solace Cloud UI shows the 'Messages Queued' section for the 'message-vpn01' queue, displaying a table with 2 messages. The table columns include Message ID, Spooled Time, Content Size (B), Attachment Size (B), Priority, Undelivered, Redeliveries, DMQ Eligible, and Replication State. The messages are listed with IDs 2 and 3, both spooled at 2023-08-09 22:10:21 and 2023-08-09 22:12:16 respectively, with content and attachment sizes of 0 and 42 bytes. Both messages are undelivered and not replicated.

Message ID	Spooled Time	Content Size (B)	Attachment Size (B)	Priority	Undelivered	Redeliveries	DMQ Eligible	Replication State
2	2023-08-09 22:10:21	0	42		Yes	0	No	Not replicated
3	2023-08-09 22:12:16	0	42		Yes	0	No	Not replicated

Practice some pub sub program:

