

Wusik SP22

William Kalfelz

www.Wusik.com (c) 2019


Table of Contents

Introduction	3
Interface	4
Wusik SP22	4
Resizing the Interface	4
Buttons and Knobs	5
Options	5
Keyboard Usage	6
Crossfading	6

Introduction

Interface

Wusik SP22



Wusik SP22 is a Sample Recording App/Plugin (Standalone Application and VST2/VST3/AU Plugins) that allows you to sample/record, edit, loop, process and even playback the input audio.

If you are using it as a Plugin, all the audio and settings gets saved in the host project file.


If you want to use the audio in a synth like Wusik Station, click on Options and Export the file.

Resizing the Interface



You can change the size of the interface by using the small triangle at the bottom-right. Just click and drag it around to set the size.

Buttons and Knobs



(1) In the Standalone version you can click on Audio Config to open the Audio/MIDI Settings.

(2) Playback Button, will play one time if not looped, or will play and loop until Stop (3) is pressed.

(3) Stop Playback/Recording.

(4) Prepare to Record. When you click it, it will wait until the audio goes over the (5) Detection Level, or if you have enabled (6) MIDI Recording, until you play a note.

(5) Recording Detection Level. When the audio goes over this value and Record was pressed, recording will start. And will only stop when there are two seconds of silence below the detection level or if (3) Stop is pressed. Or, in the case of (6) MIDI Recording, until you release the note you just pressed.

(7) Looped On/Off.

(8) Loop Start.

(9) Loop End.

(10) Options: Fade In/Out, Crossfade, Export to WAV and Normalize.

By default normalization is ON. To disable click on Options and click on Auto Normalize.

Options



(1) The first two Fade options will apply to the whole audio.

(2) The Quick Fade options will only apply to the start of the sample - Fade In - or the end of the sample - Fade Out. And only for 200 samples.

(3) Auto Normalize will lower or raise the audio level by checking the loudest volume in the entire sample.

(4) Crossfade will use the audio before the sample start to do a X crossfade between that audio and the rest of


the audio after the sample start.

Keyboard Usage



Parameters - such as the Knobs - can also be changed with the computer keyboard using the up/down arrow keys. Click on a parameter and use the keys to change the value.

Crossfading



This is how the crossfade works. The audio before the sample start is ramped up and mixed with the audio after the sample start ramped down. That's why it is called X Crossfade. Note that you need enough samples before the sample start to fit inside the whole sample start -> sample end. So the initial samples must be larger or equal to the size of the loop.