

# main.c File Reference

---

: Main program body [More...](#)

```
#include "main.h"
#include "adc.h"
#include "tim.h"
#include "usart.h"
#include "gpio.h"
#include <string.h>
#include <stdio.h>
#include <stdlib.h>
```

## Macros

---

#define	<b>UART_TX_BUFFER_SIZE</b>	64	Buffer size for transmission used in the shell communication.
#define	<b>UART_RX_BUFFER_SIZE</b>	1	Buffer size for reception used in the shell communication.
#define	<b>CMD_BUFFER_SIZE</b>	64	Buffer size for the shell command line.
#define	<b>MAX_ARGS</b>	9	Maximum number of arguments for a command in the shell script.
#define	<b>ASCII_CR</b>	0x0D	Defines CR, carriage return command in the shell.
#define	<b>ASCII_DEL</b>	0x7F	Defines DEL, delete command in the shell
#define	<b>SPEED_MAX</b>	512	Arbitrary number representing out maximum value for the motor speed.
#define	<b>TIMCLOCK</b>	170000000	Definition of bus frequency for clock, useful to calculate time.
#define	<b>PRESCALAR</b>	1	Definition of prescaler clock, useful to calculate time.

## Functions

---

void	<b>SystemClock_Config</b>	(void)	System Clock Configuration. <a href="#">More...</a>
void	<b>HAL_TIM_IC_CaptureCallback</b>	(TIM_HandleTypeDef *htim)	
int	<b>main</b>	(void)	The application entry point. <a href="#">More...</a>
void	<b>HAL_UART_RxCpltCallback</b>	(UART_HandleTypeDef *huart)	

void **powerUpSequence** (void)

void **HAL\_TIM\_PeriodElapsedCallback** (TIM\_HandleTypeDef \*htim)

Period elapsed callback in non blocking mode. More...

void **Error\_Handler** (void)

This function is executed in case of error occurrence. More...

## Variables

const uint8\_t **prompt** [] ="user@Nucleo-STM32G431>>"

Shell prompt text.

const uint8\_t **started** []

Startup message when shell is initialized. More...

const uint8\_t **newLine** [] ="r\n"

Defines characters used to create a new line.

const uint8\_t **cmdNotFound** [] ="Command not foundr\n"

Shell message for when a user input command is not implemented.

const uint8\_t **help** []

Shell message for when the user types "help". More...

const uint8\_t **pinout** []

Shell message that lists the pinout list of the microcontroller. More...

const uint8\_t **powerOn** []

Shell message when powering on the motor. More...

const uint8\_t **powerOff** []

Shell message when powering off the motor. More...

const char \* **separators** = " ="

List of separators used to parse the strings in shell.

uint32\_t **uartRxReceived**

Set to 1 when a new character is received on uart 2.

uint8\_t **uartRxBuffer** [UART\_RX\_BUFFER\_SIZE]

A buffer to store the received data from UART.

uint8\_t **uartTxBuffer** [UART\_TX\_BUFFER\_SIZE]

A buffer to store the UART data to be transmitted.

uint32\_t **IC\_Val1** = 0

First timer value.

uint32\_t **IC\_Val2** = 0

Second timer value.

uint32\_t **Difference** = 0

Difference of the two timer values, to be able to know the direction of the rotation.

int **Is\_First\_Captured** = 0

Set to 1 when the first rising edge is captured.

int **Is\_First\_Captured\_2** = 0

Set to 1 when the first rising edge is captured (version 2)

```
float frequency = 0
```

Declaration of variable to hold the frequency value.

## Detailed Description

: Main program body

### Attention

Copyright (c) 2022 STMicroelectronics. All rights reserved.

This software is licensed under terms that can be found in the LICENSE file in the root directory of this software component. If no LICENSE file comes with this software, it is provided AS-IS.

## Function Documentation

### ◆ Error\_Handler()

```
void Error_Handler ( void )
```

This function is executed in case of error occurrence.

#### Return values

**None**

### ◆ HAL\_TIM\_PeriodElapsedCallback()

```
void HAL_TIM_PeriodElapsedCallback ( TIM_HandleTypeDef * htim )
```

Period elapsed callback in non blocking mode.

#### Note

This function is called when TIM6 interrupt took place, inside HAL\_TIM\_IRQHandler(). It makes a direct call to HAL\_IncTick() to increment a global variable "uwTick" used as application time base.

#### Parameters

**htim** : TIM handle

#### Return values

**None**

### ◆ main()

```
int main ( void )
```

The application entry point.

#### Return values

**int**

- < Initializes a cmd list to store the characters sent via shell
- < Initializes an index used to parse through the shell characters
- < Initializes a variable to hold the arguments of a function
- < Initializes a variable to hold the argc value
- < Initializes a variable to hold the tokens from strtok function
- < Initializes a variable to verify if shell has finished user input
- < Initializes a variable to hold the speed value
- < Initializes a variable to hold the value in the compare register channel 1
- < Initializes a variable to hold the value in the compare register channel 2
- < Initializes a variable to hold the value form the ADC conversion for the current

### ◆ powerUpSequence()

```
void powerUpSequence ( void )
```

Sends the required sequence to power up the motor

#### Parameters

[in] **None**

[out] **None**

### ◆ SystemClock\_Config()

```
void SystemClock_Config ( void )
```

System Clock Configuration.

#### Return values

**None**

Configure the main internal regulator output voltage

Initializes the RCC Oscillators according to the specified parameters in the RCC\_OscInitTypeDef structure.

Initializes the CPU, AHB and APB buses clocks

## Variable Documentation

---

### ◆ help

```
const uint8_t help[]
```

#### Initial value:

```
=
    "\r\n*-----*"
    "\r\n| Help Menu |"
    "\r\n*-----*"
    "\r\n*set PA5 1 : Turns ON the LED*"
    "\r\n*set PA5 0 : Turns OFF the LED*"
    "\r\n*get : Prints the current and the frequency in the motor*"
    "\r\n*pinout : Prints the pinout list*"
    "\r\n*start : Starts the motor*"
    "\r\n*speed x : Sets the speed of the motor to x (-512 < x < 512)*"
    "\r\n"
```

Shell message for when the user types "help".

### ◆ pinout

```
const uint8_t pinout[]
```

#### Initial value:

```
=
    "\r\n*-----*"
    "\r\n| Pinout List |"
    "\r\n*-----*"
    "\r\n*PA0: ADC_CURRENT*"
    "\r\n*PA5: LED*"
    "\r\n*PA8: TIM1_CH1*"
    "\r\n*PA9: TIM1_CH2*"
    "\r\n*PA11: TIM1_CH1N*"
    "\r\n*PA12: TIM1_CH2N*"
    "\r\n*PC3: ISO_RESET*"
    "\r\n"
```

Shell message that lists the pinout list of the microcontroller.

#### ◆ powerOff

```
const uint8_t powerOff[]
```

#### Initial value:

```
=
    "\r\n*-----*"
    "\r\n| Motor OFF |"
    "\r\n"
```

Shell message when powering off the motor.

#### ◆ powerOn

```
const uint8_t powerOn[]
```

#### Initial value:

```
=
    "\r\n*-----*"
    "\r\n| Motor ON |"
    "\r\n"
```

Shell message when powering on the motor.

#### ◆ started

```
const uint8_t started[]
```

**Initial value:**

```
=  
    "\r\n*-----*"   
    "\r\n| Welcome on Nucleo-STM32G431 |"   
    "\r\n*-----*"   
    "\r\n"
```

Startup message when shell is initialized.