



- Expert Verified, Online, Free.

MENU



Google Discussions



Exam Associate Cloud Engineer All Questions

View all questions & answers for the Associate Cloud Engineer exam

Go to Exam

EXAM ASSOCIATE CLOUD ENGINEER TOPIC 1 QUESTION 138 DISCUSSION

Actual exam question from Google's Associate Cloud Engineer

Question #: 138

Topic #: 1

[\[All Associate Cloud Engineer Questions\]](#)

You have downloaded and installed the gcloud command line interface (CLI) and have authenticated with your Google Account. Most of your Compute Engine instances in your project run in the europe-west1-d zone. You want to avoid having to specify this zone with each CLI command when managing these instances. What should you do?

- A. Set the europe-west1-d zone as the default zone using the gcloud config subcommand.
- B. In the Settings page for Compute Engine under Default location, set the zone to europe-west1-d.
- C. In the CLI installation directory, create a file called default.conf containing zone=europe-west1-d.
- D. Create a Metadata entry on the Compute Engine page with key compute/zone and value europe-west1-d.

Show Suggested Answer

by [filco72](#) at Aug. 11, 2020, 2:11 p.m.

Comments

Type your comment...

Submit

🗨️ 👤 **ESP_SAP** Highly Voted 4 years, 2 months ago

Correct Answer is (A):

Change your default zone and region in the metadata server

Note: This only applies to the default configuration.

You can change the default zone and region in your metadata server by making a request to the metadata server. For example:

```
gcloud compute project-info add-metadata \
--metadata google-compute-default-region=europe-west1,google-compute-default-zone=europe-west1-b
```

The gcloud command-line tool only picks up on new default zone and region changes after you rerun the gcloud init command. After updating your default metadata, run gcloud init to reinitialize your default configuration.

https://cloud.google.com/compute/docs/gcloud-compute#change_your_default_zone_and_region_in_the_metadata_server

👍 ↩ 🚩 upvoted 29 times

🗨️ 👤 **Examan1** 3 years, 7 months ago

Using gcloud config you can set the zone in your active configuration only. This setting does not apply to other gcloud configurations and does not become the default for the project.

Ref: <https://cloud.google.com/sdk/gcloud/reference/config/set>

So I believe correct answer is B as per <https://cloud.google.com/compute/docs/regions-zones/changing-default-zone-region#console>

In the Cloud Console, go to the Settings page.

From the Zone drop-down menu, select a default zone.

👍 ↩ 🚩 upvoted 4 times

🗨️ 👤 **tavva_prudhvi** 3 years, 6 months ago

bro, it mentioned going into the console settings, not the compute engine settings!

To change your default region or zone:

In the Cloud Console, go to the Settings page.

Go to the Settings page

From the Region drop-down menu, select a default region.

From the Zone drop-down menu, select a default zone.

👍 ↩ 🚩 upvoted 1 times

🗨️ 👤 **jcloud965** 3 years, 3 months ago

This setting in the Cloud Console won't be taken into account for gcloud on your active config

👍 ↩ 🚩 upvoted 2 times

🗨️ 👤 **xtian2900** 4 years, 1 month ago

does your comment imply that the answer is D ? i'm confused

👍 ↩ 🚩 upvoted 3 times

🗨️ 👤 **mahesh0049** 2 years, 9 months ago

every thing is correct in your explanation but instead of using gcloud compute command they used gcloud config.

👍 ↩ 🚩 upvoted 4 times

🗨️ 👤 **bobthebuilder55110** 2 years, 2 months ago

You can use the gcloud config set command here, https://cloud.google.com/compute/docs/gcloud-compute#set_default_zone_and_region_in_your_local_client

👍 ↩ 🚩 upvoted 4 times

🗨️ 👤 **dttncl** 3 years ago

I agree the answer is A.

gcloud config - view and edit Cloud SDK properties

zone

Default zone to use when working with zonal Compute Engine resources.

<https://cloud.google.com/sdk/gcloud/reference/config>

👍 ↩ 🚩 upvoted 3 times

SSPC Highly Voted 4 years, 2 months ago

I would go with the answer A

upvoted 11 times

blackBeard33 Most Recent 8 months, 2 weeks ago

Selected Answer: A

I would choose A

reference : <https://cloud.google.com/sdk/gcloud/reference/config/set>

upvoted 1 times

VijKall 11 months, 3 weeks ago

Selected Answer: A

gcloud config set compute/zone europe-west1-b

upvoted 1 times

Captain1212 1 year, 1 month ago

Selected Answer: A

A is the correct answer, just set default in cloud console in the starting by the cloud shell commands

upvoted 1 times

tatyavinchu 1 year, 2 months ago

Correct Answer is A

upvoted 1 times

GokuVelusaamy 1 year, 9 months ago

Selected Answer: A

We can set the default zone using the below CLI command,

gcloud config set compute/zone ZONE

Refer : https://cloud.google.com/compute/docs/gcloud-compute#set_default_zone_and_region_in_your_local_client

upvoted 1 times

Angel_99 2 years, 2 months ago

Selected Answer: A

It is clearly mentioned it is to be done via CLI not console

upvoted 1 times

AzureDP900 2 years, 4 months ago

A is right

upvoted 1 times

Tirthankar17 2 years, 4 months ago

Selected Answer: A

A, it is clearly mentioned it is to be done via CLI not console.

upvoted 1 times

pfabio 2 years, 4 months ago

Selected Answer: A

Just run this command on CLI

gcloud config set compute/zone ZONE

upvoted 1 times

Rukman 2 years, 7 months ago

Selected Answer: A

Ans: A

"You want to avoid having to specify this zone with each CLI command"
its about CLI not console!

upvoted 2 times

injarapu 2 years, 7 months ago

Selected Answer: B

<https://cloud.google.com/compute/docs/regions-zones/changing-default-zone-region#console>

upvoted 2 times

oracle111 2 years, 8 months ago

Selected Answer: A

Selected Answer: A

<https://cloud.google.com/compute/docs/gcloud-compute>

gcloud config set compute/zone ZONE

👍 ↩ 🚩 upvoted 3 times

🗨️ 👤 ElenaL 2 years, 9 months ago

Selected Answer: A

in GCP qwiklabs, this is how they ask you set the zone primarily, so I go with A

👍 ↩ 🚩 upvoted 1 times

🗨️ 👤 Raju44 2 years, 9 months ago

Answer A. There is no file like default.config. In my labs i set default values Zone/Region/project etc default values stored in the following location

cat ~/.config/gcloud/configurations/config_default.

We can also set zone default using " gcloud config set compute/zone <zona_name>"

👍 ↩ 🚩 upvoted 2 times

🗨️ 👤 jaffarali 2 years, 10 months ago

A is the right option

👍 ↩ 🚩 upvoted 1 times

[Load full discussion...](#)

Start Learning for free



Social Media

[Facebook](#) , [Twitter](#)

[YouTube](#) , [Reddit](#)

[Pinterest](#)

EXAMTOPICS

We are the biggest and most updated IT certification exam material website.

Using our own resources, we strive to strengthen the IT professionals community for free.



© 2024 ExamTopics

ExamTopics doesn't offer Real Microsoft Exam Questions. ExamTopics doesn't offer Real Amazon Exam Questions. ExamTopics

Materials do not contain actual questions and answers from Cisco's Certification Exams.

CFA Institute does not endorse, promote or warrant the accuracy or quality of ExamTopics. CFA® and Chartered Financial Analyst® are registered trademarks owned by CFA Institute.