


The system allows you to check pages for broken links. Only links within `<a>`, ``, `<script>` and `<link>` elements are validated by the link checker.

1. Open the **Pages** application.
2. Select a page in the content tree.
3. Switch to **Preview** mode.
4. Open the **Validate -> Link checker** tab.
5. Click **Validate**.



Status code	Type	Error message	URL	Request time
Redirect -> OK	W	redirects to http://localhost/KenticoCMS_8.0.0219/CMSPages/logo.aspx?ReturnUrl=%2FKenticoCMS_8.0.0219%2FAdmin%2FCMSAdministration.aspx%3Fusername%3Dadministrator&username=administrator OK	http://localhost/KenticoCMS_8.0.0219/CMSPages/logo.aspx?ReturnUrl=%2FKenticoCMS_8.0.0219%2FAdmin%2FCMSAdministration.aspx%3Fusername%3Dadministrator	118 ms
Redirect -> OK	W	redirects to http://localhost/KenticoCMS_8.0.0219/SpecialPages/My-account.aspx?ReturnUrl=%2FKenticoCMS_8.0.0219%2FSpecialPages/My-account.aspx OK	http://localhost/KenticoCMS_8.0.0219/SpecialPages/My-account.aspx?ReturnUrl=%2FKenticoCMS_8.0.0219%2FSpecialPages/My-account.aspx	6714 ms
Redirect -> OK	W	redirects to http://localhost/KenticoCMS_8.0.0219/SpecialPages/E-shop/Wishlist.aspx?ReturnUrl=%2FKenticoCMS_8.0.0219%2FSpecialPages/E-shop/Wishlist.aspx OK	http://localhost/KenticoCMS_8.0.0219/SpecialPages/E-shop/Wishlist.aspx?ReturnUrl=%2FKenticoCMS_8.0.0219%2FSpecialPages/E-shop/Wishlist.aspx	29 ms

If the validator finds broken links on the page, you can view the following information for each detected issue:

- **Status code** - the HTML status code returned when the link is accessed. Statuses of redirected links are shown for each page within the redirection.
- **Type** - W for links redirected to a different location (301 status code), E for broken links (404 status code).
- **Error message** - details about the link issue.
- **URL** - URL to which the link is pointing.
- **Request time** - time elapsed between sending a request to the link and receiving a response.